Implementing Multiple Precision Arithmetic

Holiday Draft Edition

Tom St Denis Algonquin College

Mads Rasmussen Open Communications Security

 $\begin{array}{c} {\rm Greg~Rose} \\ {\rm QUALCOMM~Australia} \end{array}$

January 25, 2004

This text has been placed in the public domain. This text corresponds to the v0.28 release of the LibTomMath project.

Tom St Denis 111 Banning Rd Ottawa, Ontario K2L 1C3 Canada

Phone: 1-613-836-3160 Email: tomstdenis@iahu.ca

This text is formatted to the international B5 paper size of 176mm wide by 250mm tall using the LaTeX book macro package and the Perl booker package.

Contents

Intr	\mathbf{oduct}	ion 1	L
1.1	Multip	ple Precision Arithmetic	1
	1.1.1	What is Multiple Precision Arithmetic?	1
	1.1.2	The Need for Multiple Precision Arithmetic	1
	1.1.3	Benefits of Multiple Precision Arithmetic	3
1.2	Purpo	se of This Text	4
1.3	Discus	ssion and Notation	5
	1.3.1	Notation	5
	1.3.2	Precision Notation	ŏ
	1.3.3	Algorithm Inputs and Outputs	ŝ
	1.3.4	Mathematical Expressions	ŝ
	1.3.5	Work Effort	7
1.4	Exerci	ses	7
1.5	Introd	uction to LibTomMath	9
	1.5.1	What is LibTomMath?	9
	1.5.2	Goals of LibTomMath	9
1.6	Choice	e of LibTomMath)
	1.6.1	Code Base)
	1.6.2	API Simplicity	1
	1.6.3	Optimizations	1
	1.6.4	Portability and Stability	1
	1.6.5	Choice	2
Get	ting S	tarted 13	3
2.1	_		3
2.2		· ·	1
	2.2.1		5
	1.1 1.2 1.3 1.4 1.5 1.6	1.1 Multip 1.1.1 1.1.2 1.1.3 1.2 Purpo 1.3 Discus 1.3.1 1.3.2 1.3.3 1.3.4 1.3.5 1.4 Exerci 1.5 Introd 1.5.1 1.5.2 1.6 Choice 1.6.1 1.6.2 1.6.3 1.6.4 1.6.5 Getting S 2.1 Librar 2.2 What	1.1 Multiple Precision Arithmetic 1 1.1.1 What is Multiple Precision Arithmetic? 1 1.1.2 The Need for Multiple Precision Arithmetic 1 1.1.3 Benefits of Multiple Precision Arithmetic 1 1.2 Purpose of This Text 4 1.3 Discussion and Notation 5 1.3.1 Notation 5 1.3.2 Precision Notation 5 1.3.3 Algorithm Inputs and Outputs 6 1.3.4 Mathematical Expressions 6 1.3.5 Work Effort 7 1.4 Exercises 5 1.5 Introduction to LibTomMath 9 1.5.1 What is LibTomMath 9 1.5.2 Goals of LibTomMath 9 1.6.1 Code Base 16 1.6.2 API Simplicity 11 1.6.3 Optimizations 12 1.6.4 Portability and Stability 13 1.6.5 Choice 12 Getting Started 2.1 Library Basics 13 2.2 What is a Multiple Precision Integer? 14

	2.3 2.4 2.5	Argument Passing17Return Values17Initialization and Clearing182.5.1 Initializing an mp_int192.5.2 Clearing an mp_int21	7 8 9
	2.6	Maintenance Algorithms252.6.1 Augmenting an mp_int's Precision252.6.2 Initializing Variable Precision mp_ints26	3 3
		2.6.3 Multiple Integer Initializations and Clearings	
3	Bas	sic Operations 33	3
	3.1	Introduction	3
	3.2	Assigning Values to mp_int Structures	3
		3.2.1 Copying an mp_int	3
		3.2.2 Creating a Clone	7
	3.3	Zeroing an Integer	3
	3.4	Sign Manipulation)
		3.4.1 Absolute Value)
		3.4.2 Integer Negation	1
	3.5	Small Constants	2
		3.5.1 Setting Small Constants	2
		3.5.2 Setting Large Constants	3
	3.6	Comparisons	1
		3.6.1 Unsigned Comparisions	1
		3.6.2 Signed Comparisons	7
4	Bas	sic Arithmetic 49)
	4.1	Introduction)
	4.2	Addition and Subtraction)
		4.2.1 Low Level Addition)
		4.2.2 Low Level Subtraction	5
		4.2.3 High Level Addition	9
		4.2.4 High Level Subtraction 62	2
	4.3	Bit and Digit Shifting 65	5
		4.3.1 Multiplication by Two 68	5
		4.3.2 Division by Two	3
	4.4	Polynomial Basis Operations	1
		4.4.1 Multiplication by $x cdots c$	1

		4.4.2	Division by $x \dots 74$
	4.5	Powers	s of Two
		4.5.1	Multiplication by Power of Two
		4.5.2	Division by Power of Two 80
		4.5.3	Remainder of Division by Power of Two 83
			V
5	Mu		tion and Squaring 87
	5.1	The M	Iultipliers
	5.2	Multip	blication
		5.2.1	The Baseline Multiplication
		5.2.2	Faster Multiplication by the "Comba" Method 93
		5.2.3	Polynomial Basis Multiplication 100
		5.2.4	Karatsuba Multiplication
		5.2.5	Toom-Cook 3-Way Multiplication
		5.2.6	Signed Multiplication
	5.3	Squari	ng
		5.3.1	The Baseline Squaring Algorithm
		5.3.2	Faster Squaring by the "Comba" Method 126
		5.3.3	Polynomial Basis Squaring
		5.3.4	Karatsuba Squaring
		5.3.5	Toom-Cook Squaring
		5.3.6	High Level Squaring
6	Mod	dular I	Reduction 141
	6.1	Basics	of Modular Reduction
	6.2	The B	arrett Reduction
		6.2.1	Fixed Point Arithmetic
		6.2.2	Choosing a Radix Point
		6.2.3	Trimming the Quotient
		6.2.4	Trimming the Residue
		6.2.5	The Barrett Algorithm
		6.2.6	The Barrett Setup Algorithm
	6.3	The M	Iontgomery Reduction
		6.3.1	Digit Based Montgomery Reduction
		6.3.2	Baseline Montgomery Reduction
		6.3.3	Faster "Comba" Montgomery Reduction 160
		6.3.4	Montgomery Setup
	6.4	The D	iminished Radix Algorithm
		6.4.1	Choice of Moduli

		$ \begin{array}{cccccccccccccccccccccccccccccccccccc$
	6.5	Algorithm Comparison
7	Exp	onentiation 183
	7.1	Exponentiation Basics
		7.1.1 Single Digit Exponentiation
	7.2	<i>k</i> -ary Exponentiation
		7.2.1 Optimal Values of k
		7.2.2 Sliding-Window Exponentiation 189
	7.3	Modular Exponentiation
		7.3.1 Barrett Modular Exponentiation 193
	7.4	Quick Power of Two
0	TT:1	
8	8.1	her Level Algorithms 205 Integer Division with Remainder
	0.1	8.1.1 Quotient Estimation
		8.1.2 Normalized Integers
		8.1.3 Radix- β Division with Remainder
	8.2	Single Digit Helpers
	0.2	8.2.1 Single Digit Addition and Subtraction
		8.2.2 Single Digit Multiplication
		8.2.3 Single Digit Division
		8.2.4 Single Digit Root Extraction
	8.3	Random Number Generation
	8.4	Formatted Representations
	0.1	8.4.1 Reading Radix-n Input
		8.4.2 Generating Radix- <i>n</i> Output
		-
9		mber Theoretic Algorithms 241
	9.1	Greatest Common Divisor
		9.1.1 Complete Greatest Common Divisor 244
	9.2	Least Common Multiple
	9.3	Jacobi Symbol Computation
		9.3.1 Jacobi Symbol
	9.4	Modular Inverse
		9.4.1 General Case
	9.5	Primality Tests

9.5.1	Trial Division											265
9.5.2	The Fermat Test \dots											268
9.5.3	The Miller-Rabin Test											269

List of Figures

1.1	Typical Data Types for the C Programming Language 2
1.2	Exercise Scoring System
2.1	Design Flow of the First Few Original LibTomMath Functions 14
2.2	Algorithm mp_init
2.3	Algorithm mp_clear
2.4	Algorithm mp_grow
2.5	Algorithm mp_init_size
2.6	Algorithm mp_init_multi
2.7	Algorithm mp_clamp
3.1	Algorithm mp_copy
3.2	Algorithm mp_init_copy
3.3	Algorithm mp_zero
3.4	Algorithm mp_abs
3.5	Algorithm mp_neg
3.6	Algorithm mp_set
3.7	Algorithm mp_set_int
3.8	Comparison Return Codes
3.9	Algorithm mp_cmp_mag
3.10	Algorithm mp_cmp
4.1	Algorithm s_mp_add
4.2	Algorithm s_mp_sub
4.3	Algorithm mp_add
4.4	Addition Guide Chart 61
4.5	Algorithm mp_sub
4.6	Subtraction Guide Chart

$4.12 \\ 4.13$	Algorithm mp_mul_2 Algorithm mp_div_2 Algorithm mp_lshd Sliding Window Movement Algorithm mp_rshd Algorithm mp_mul_2d Algorithm mp_div_2d Algorithm mp_mod_2d	66 69 72 73 75 78 81 84
5.1 5.2 5.3 5.4 5.5 5.6	Algorithm s_mp_mul_digs	96
5.7 5.8 5.9 5.10	Algorithm mp_karatsuba_mul	105 111 112 120
$5.13 \\ 5.14$	Squaring Optimization Diagram	123 127 133
6.1 6.2 6.3 6.4 6.5 6.6 6.7 6.8 6.9	Algorithm mp_reduce	150 152 152 153 153 154 155
6.10 6.11 6.12 6.13	Algorithm fast_mp_montgomery_reduce	161 166 169 170

	Algorithm mp_dr_setup
6.16	Algorithm mp_dr_is_modulus
6.17	Algorithm mp_reduce_2k
6.18	Algorithm mp_reduce_2k_setup
6.19	Algorithm mp_reduce_is_2k $\ \ldots \ 180$
7.1	Left to Right Exponentiation
7.2	Example of Left to Right Exponentiation
7.2	Algorithm mp_expt_d
7.4	k-ary Exponentiation
7.4 - 7.5	Optimal Values of k for k-ary Exponentiation
7.6	Optimal Values of k for Sliding Window Exponentiation 189
7.7	Sliding Window k-ary Exponentiation
7.8	Algorithm mp_exptmod
7.9	Algorithm s_mp_exptmod
7.10	
7.10	,
7.11	
1.12	Algorithmi imp_zexpt
8.1	Algorithm Radix- β Integer Division
8.2	Algorithm mp_div
8.3	Algorithm mp_div (continued)
8.4	Algorithm mp_add_d
8.5	Algorithm mp_mul_d
8.6	Algorithm mp_div_d
8.7	Algorithm mp_n_root
8.8	Algorithm mp_rand
8.9	Lower ASCII Map
8.10	Algorithm mp_read_radix
8.11	Algorithm mp_toradix
8.12	Example of Algorithm mp_toradix
9.1	Algorithm Greatest Common Divisor (I)
9.1	Algorithm Greatest Common Divisor (I)
$9.2 \\ 9.3$	Algorithm Greatest Common Divisor (II)
9.3 9.4	Algorithm mp_gcd
$9.4 \\ 9.5$	Algorithm mp_lcm
9.5	
9.6	Algorithm mp_jacobi
9.1	Algorithm mp_prime_is_divisible

9.8	Algorithm mp_prime_fermat	268
9.9	Algorithm mp_prime_miller_rabin	270

Prefaces to the Holiday Draft Edition

I started this text in April 2003 to complement my LibTomMath library. That is, explain how to implement the functions contained in LibTomMath. The goal is to have a textbook that any Computer Science student can use when implementing their own multiple precision arithmetic. The plan I wanted to follow was flesh out all the ideas and concepts I had floating around in my head and then work on it afterwards refining a little bit at a time. Chance would have it that I ended up with my summer off from Algonquin College and I was given four months solid to work on the text.

Choosing to not waste any time I dove right into the project even before my spring semester was finished. I wrote a bit off and on at first. The moment my exams were finished I jumped into long 12 to 16 hour days. The result after only a couple of months was a ten chapter, three hundred page draft that I quickly had distributed to anyone who wanted to read it. I had Jean-Luc Cooke print copies for me and I brought them to Crypto'03 in Santa Barbara. So far I have managed to grab a certain level of attention having people from around the world ask me for copies of the text was certain rewarding.

Now we are in December 2003. By this time I had pictured that I would have at least finished my second draft of the text. Currently I am far off from this goal. I've done partial re-writes of chapters one, two and three but they are not even finished yet. I haven't given up on the project, only had some setbacks. First O'Reilly declined to publish the text then Addison-Wesley and Greg is tried another which I don't know the name of. However, at this point I want to focus my energy onto finishing the book not securing a contract.

So why am I writing this text? It seems like a lot of work right? Most certainly it is a lot of work writing a textbook. Even the simplest introductory

material has to be lined with references and figures. A lot of the text has to be re-written from point form to prose form to ensure an easier read. Why am I doing all this work for free then? Simple. My philosophy is quite simply "Open Source. Open Academia. Open Minds" which means that to achieve a goal of open minds, that is, people willing to accept new ideas and explore the unknown you have to make available material they can access freely without hinderance.

I've been writing free software since I was about sixteen but only recently have I hit upon software that people have come to depend upon. I started LibTomCrypt in December 2001 and now several major companies use it as integral portions of their software. Several educational institutions use it as a matter of course and many freelance developers use it as part of their projects. To further my contributions I started the LibTomMath project in December 2002 aimed at providing multiple precision arithmetic routines that students could learn from. That is write routines that are not only easy to understand and follow but provide quite impressive performance considering they are all in standard portable ISO C.

The second leg of my philosophy is "Open Academia" which is where this textbook comes in. In the end, when all is said and done the text will be useable by educational institutions as a reference on multiple precision arithmetic.

At this time I feel I should share a little information about myself. The most common question I was asked at Crypto'03, perhaps just out of professional courtesy, was which school I either taught at or attended. The unfortunate truth is that I neither teach at or attend a school of academic reputation. I'm currently at Algonquin College which is what I'd like to call "somewhat academic but mostly vocational" college. In otherwords, job training.

I'm a 21 year old computer science student mostly self-taught in the areas I am aware of (which includes a half-dozen computer science fields, a few fields of mathematics and some English). I look forward to teaching someday but I am still far off from that goal.

Now it would be improper for me to not introduce the rest of the texts coauthors. While they are only contributing corrections and editorial feedback their support has been tremendously helpful in presenting the concepts laid out in the text so far. Greg has always been there for me. He has tracked my LibTom projects since their inception and even sent cheques to help pay tuition from time to time. His background has provided a wonderful source to bounce ideas off of and improve the quality of my writing. Mads is another fellow who has just "been there". I don't even recall what his interest in the LibTom projects is but I'm definitely glad he has been around. His ability to catch logical errors in my written English have saved me on several occasions to say the least. What to expect next? Well this is still a rough draft. I've only had the chance to update a few chapters. However, I've been getting the feeling that people are starting to use my text and I owe them some updated material. My current tenative plan is to edit one chapter every two weeks starting January 4th. It seems insane but my lower course load at college should provide ample time. By Crypto'04 I plan to have a 2nd draft of the text polished and ready to hand out to as many people who will take it.

Finally, again, I'd like to thank my parents Vern and Katie St Denis for giving me a place to stay, food, clothes and word of encouragement whenever I seemed to need it. Thanks!

Tom St Denis

I found the opportunity to work with Tom appealing for several reasons, not only could I broaden my own horizons, but also contribute to educate others facing the problem of having to handle big number mathematical calculations.

This book is Tom's child and he has been caring and fostering the project ever since the beginning with a clear mind of how he wanted the project to turn out. I have helped by proofreading the text and we have had several discussions about the layout and language used.

I hold a masters degree in cryptography from the University of Southern Denmark and have always been interested in the practical aspects of cryptography.

Having worked in the security consultancy business for several years in São Paulo, Brazil, I have been in touch with a great deal of work in which multiple precision mathematics was needed. Understanding the possibilities for speeding up multiple precision calculations is often very important since we deal with outdated machine architecture where modular reductions, for example, become painfully slow.

This text is for people who stop and wonder when first examining algorithms such as RSA for the first time and asks themselves, "You tell me this is only secure for large numbers, fine; but how do you implement these numbers?"

Mads Rasmussen São Paulo - SP Brazil It's all because I broke my leg. That just happened to be at about the same time that Tom asked for someone to review the section of the book about Karatsuba multiplication. I was laid up, alone and immobile, and thought "Why not?" I vaguely knew what Karatsuba multiplication was, but not really, so I thought I could help, learn, and stop myself from watching daytime cable TV, all at once.

At the time of writing this, I've still not met Tom or Mads in meatspace. I've been following Tom's progress since his first splash on the sci.crypt Usenet news group. I watched him go from a clueless newbie, to the cryptographic equivalent of a reformed smoker, to a real contributor to the field, over a period of about two years. I've been impressed with his obvious intelligence, and astounded by his productivity. Of course, he's young enough to be my own child, so he doesn't have my problems with staying awake.

When I reviewed that single section of the book, in its very earliest form, I was very pleasantly surprised. So I decided to collaborate more fully, and at least review all of it, and perhaps write some bits too. There's still a long way to go with it, and I have watched a number of close friends go through the mill of publication, so I think that the way to go is longer than Tom thinks it is. Nevertheless, it's a good effort, and I'm pleased to be involved with it.

Greg Rose, Sydney, Australia, June 2003.

Chapter 1

Introduction

1.1 Multiple Precision Arithmetic

1.1.1 What is Multiple Precision Arithmetic?

When we think of long-hand arithmetic such as addition or multiplication we rarely consider the fact that we instinctively raise or lower the precision of the numbers we are dealing with. For example, in decimal we almost immediate can reason that 7 times 6 is 42. However, 42 has two digits of precision as opposed to one digit we started with. Further multiplications of say 3 result in a larger precision result 126. In these few examples we have multiple precisions for the numbers we are working with. Despite the various levels of precision a single subset of algorithms can be designed to accommodate them.

By way of comparison a fixed or single precision operation would lose precision on various operations. For example, in the decimal system with fixed precision $6 \cdot 7 = 2$.

Essentially at the heart of computer based multiple precision arithmetic are the same long-hand algorithms taught in schools to manually add, subtract, multiply and divide.

1.1.2 The Need for Multiple Precision Arithmetic

The most prevalent need for multiple precision arithmetic, often referred to as "bignum" math, is within the implementation of public-key cryptography

¹With the occasional optimization.

algorithms. Algorithms such as RSA [11] and Diffie-Hellman [12] require integers of significant magnitude to resist known cryptanalytic attacks. For example, at the time of this writing a typical RSA modulus would be at least greater than 10^{309} . However, modern programming languages such as ISO C [18] and Java [19] only provide instrinsic support for integers which are relatively small and single precision.

Data Type	Range
char	$-128 \dots 127$
short	$-32768 \dots 32767$
long	$-2147483648\dots 2147483647$
long long	$-9223372036854775808\dots 9223372036854775807$

Figure 1.1: Typical Data Types for the C Programming Language

The largest data type guaranteed to be provided by the ISO C programming language² can only represent values up to 10^{19} as shown in figure 1.1. On its own the C language is insufficient to accommodate the magnitude required for the problem at hand. An RSA modulus of magnitude 10^{19} could be trivially factored³ on the average desktop computer, rendering any protocol based on the algorithm insecure. Multiple precision algorithms solve this very problem by extending the range of representable integers while using single precision data types.

Most advancements in fast multiple precision arithmetic stem from the need for faster and more efficient cryptographic primitives. Faster modular reduction and exponentiation algorithms such as Barrett's algorithm, which have appeared in various cryptographic journals, can render algorithms such as RSA and Diffie-Hellman more efficient. In fact, several major companies such as RSA Security, Certicom and Entrust have built entire product lines on the implementation and deployment of efficient algorithms.

However, cryptography is not the only field of study that can benefit from fast multiple precision integer routines. Another auxiliary use of multiple precision integers is high precision floating point data types. The basic IEEE [13] standard floating point type is made up of an integer mantissa q, an exponent e and a sign bit s. Numbers are given in the form $n = q \cdot b^e \cdot -1^s$ where b = 2

²As per the ISO C standard. However, each compiler vendor is allowed to augment the precision as they see fit.

³A Pollard-Rho factoring would take only 2¹⁶ time.

is the most common base for IEEE. Since IEEE floating point is meant to be implemented in hardware the precision of the mantissa is often fairly small (23, 48 and 64 bits). The mantissa is merely an integer and a multiple precision integer could be used to create a mantissa of much larger precision than hardware alone can efficiently support. This approach could be useful where scientific applications must minimize the total output error over long calculations.

Another use for large integers is within arithmetic on polynomials of large characteristic (i.e. GF(p)[x] for large p). In fact the library discussed within this text has already been used to form a polynomial basis library⁴.

1.1.3 Benefits of Multiple Precision Arithmetic

The benefit of multiple precision representations over single or fixed precision representations is that no precision is lost while representing the result of an operation which requires excess precision. For example, the product of two n-bit integers requires at least 2n bits of precision to be represented faithfully. A multiple precision algorithm would augment the precision of the destination to accommodate the result while a single precision system would truncate excess bits to maintain a fixed level of precision.

It is possible to implement algorithms which require large integers with fixed precision algorithms. For example, elliptic curve cryptography (ECC) is often implemented on smartcards by fixing the precision of the integers to the maximum size the system will ever need. Such an approach can lead to vastly simpler algorithms which can accommodate the integers required even if the host platform cannot natively accommodate them⁵. However, as efficient as such an approach may be, the resulting source code is not normally very flexible. It cannot, at runtime, accommodate inputs of higher magnitude than the designer anticipated.

Multiple precision algorithms have the most overhead of any style of arithmetic. For the the most part the overhead can be kept to a minimum with careful planning, but overall, it is not well suited for most memory starved platforms. However, multiple precision algorithms do offer the most flexibility in terms of the magnitude of the inputs. That is, the same algorithms based on multiple precision integers can accommodate any reasonable size input without the designer's explicit forethought. This leads to lower cost of ownership for the code as it only has to be written and tested once.

⁴See http://poly.libtomcrypt.org for more details.

⁵For example, the average smartcard processor has an 8 bit accumulator.

1.2 Purpose of This Text

The purpose of this text is to instruct the reader regarding how to implement efficient multiple precision algorithms. That is to not only explain a limited subset of the core theory behind the algorithms but also the various "house keeping" elements that are neglected by authors of other texts on the subject. Several well reknowned texts [1, 2] give considerably detailed explanations of the theoretical aspects of algorithms and often very little information regarding the practical implementation aspects.

In most cases how an algorithm is explained and how it is actually implemented are two very different concepts. For example, the Handbook of Applied Cryptography (HAC), algorithm 14.7 on page 594, gives a relatively simple algorithm for performing multiple precision integer addition. However, the description lacks any discussion concerning the fact that the two integer inputs may be of differing magnitudes. As a result the implementation is not as simple as the text would lead people to believe. Similarly the division routine (algorithm 14.20, pp. 598) does not discuss how to handle sign or handle the dividend's decreasing magnitude in the main loop (step #3).

Both texts also do not discuss several key optimal algorithms required such as "Comba" and Karatsuba multipliers and fast modular inversion, which we consider practical oversights. These optimal algorithms are vital to achieve any form of useful performance in non-trivial applications.

To solve this problem the focus of this text is on the practical aspects of implementing a multiple precision integer package. As a case study the "LibTom-Math" package is used to demonstrate algorithms with real implementations that have been field tested and work very well. The LibTomMath library is freely available on the Internet for all uses and this text discusses a very large portion of the inner workings of the library.

The algorithms that are presented will always include at least one "pseudocode" description followed by the actual C source code that implements the algorithm. The pseudo-code can be used to implement the same algorithm in other programming languages as the reader sees fit.

This text shall also serve as a walkthrough of the creation of multiple precision algorithms from scratch. Showing the reader how the algorithms fit together as well as where to start on various taskings.

⁶Available at http://math.libtomcrypt.org

⁷In the ISO C programming language.

1.3 Discussion and Notation

1.3.1 Notation

A multiple precision integer of *n*-digits shall be denoted as $x = (x_{n-1}...x_1x_0)_{\beta}$ and represent the integer $x \equiv \sum_{i=0}^{n-1} x_i \beta^i$. The elements of the array x are said to be the radix β digits of the integer. For example, $x = (1, 2, 3)_{10}$ would represent the integer $1 \cdot 10^2 + 2 \cdot 10^1 + 3 \cdot 10^0 = 123$.

The term "mp_int" shall refer to a composite structure which contains the digits of the integer it represents, as well as auxilary data required to manipulate the data. These additional members are discussed further in section 2.2.1. For the purposes of this text a "multiple precision integer" and an "mp_int" are assumed to be synonymous. When an algorithm is specified to accept an mp_int variable it is assumed the various auxiliary data members are present as well. An expression of the type variablename.item implies that it should evaluate to the member named "item" of the variable. For example, a string of characters may have a member "length" which would evaluate to the number of characters in the string. If the string a equals "hello" then it follows that a.length = 5.

For certain discussions more generic algorithms are presented to help the reader understand the final algorithm used to solve a given problem. When an algorithm is described as accepting an integer input it is assumed the input is a plain integer with no additional multiple-precision members. That is, algorithms that use integers as opposed to mp_ints as inputs do not concern themselves with the housekeeping operations required such as memory management. These algorithms will be used to establish the relevant theory which will subsequently be used to describe a multiple precision algorithm to solve the same problem.

1.3.2 Precision Notation

For the purposes of this text a single precision variable must be able to represent integers in the range $0 \le x < q\beta$ while a double precision variable must be able to represent integers in the range $0 \le x < q\beta^2$. The variable β represents the radix of a single digit of a multiple precision integer and must be of the form q^p for $q, p \in \mathbb{Z}^+$. The extra radix-q factor allows additions and subtractions to proceed without truncation of the carry. Since all modern computers are binary, it is assumed that q is two, for all intents and purposes.

Within the source code that will be presented for each algorithm, the data type **mp_digit** will represent a single precision integer type, while, the data type **mp_word** will represent a double precision integer type. In several algorithms

(notably the Comba routines) temporary results will be stored in arrays of double precision mp_words. For the purposes of this text x_j will refer to the j'th digit of a single precision array and \hat{x}_j will refer to the j'th digit of a double precision array. Whenever an expression is to be assigned to a double precision variable it is assumed that all single precision variables are promoted to double precision during the evaluation. Expressions that are assigned to a single precision variable are truncated to fit within the precision of a single precision data type.

For example, if $\beta=10^2$ a single precision data type may represent a value in the range $0 \le x < 10^3$, while a double precision data type may represent a value in the range $0 \le x < 10^5$. Let a=23 and b=49 represent two single precision variables. The single precision product shall be written as $c \leftarrow a \cdot b$ while the double precision product shall be written as $\hat{c} \leftarrow a \cdot b$. In this particular case, $\hat{c}=1127$ and c=127. The most significant digit of the product would not fit in a single precision data type and as a result $c \ne \hat{c}$.

1.3.3 Algorithm Inputs and Outputs

Within the algorithm descriptions all variables are assumed to be scalars of either single or double precision as indicated. The only exception to this rule is when variables have been indicated to be of type mp_int. This distinction is important as scalars are often used as array indicies and various other counters.

1.3.4 Mathematical Expressions

The $\lfloor \rfloor$ brackets imply an expression truncated to an integer not greater than the expression itself. For example, $\lfloor 5.7 \rfloor = 5$. Similarly the $\lceil \rceil$ brackets imply an expression rounded to an integer not less than the expression itself. For example, $\lceil 5.1 \rceil = 6$. Typically when the / division symbol is used the intention is to perform an integer division with truncation. For example, $\lceil 5/2 \rceil = 2$ which will often be written as $\lfloor 5/2 \rfloor = 2$ for clarity. When an expression is written as a fraction a real value division is implied, for example $\frac{5}{2} = 2.5$.

The norm of a multiple precision integer, for example, ||x|| will be used to represent the number of digits in the representation of the integer. For example, ||123|| = 3 and ||79452|| = 5.

1.4. EXERCISES 7

1.3.5 Work Effort

To measure the efficiency of the specified algorithms, a modified big-Oh notation is used. In this system all single precision operations are considered to have the same cost⁸. That is a single precision addition, multiplication and division are assumed to take the same time to complete. While this is generally not true in practice, it will simplify the discussions considerably.

Some algorithms have slight advantages over others which is why some constants will not be removed in the notation. For example, a normal baseline multiplication (section 5.2.1) requires $O(n^2)$ work while a baseline squaring (section 5.3) requires $O(\frac{n^2+n}{2})$ work. In standard big-Oh notation these would both be said to be equivalent to $O(n^2)$. However, in the context of the this text this is not the case as the magnitude of the inputs will typically be rather small. As a result small constant factors in the work effort will make an observable difference in algorithm efficiency.

All of the algorithms presented in this text have a polynomial time work level. That is, of the form $O(n^k)$ for $n, k \in \mathbb{Z}^+$. This will help make useful comparisons in terms of the speed of the algorithms and how various optimizations will help pay off in the long run.

1.4 Exercises

Within the more advanced chapters a section will be set aside to give the reader some challenging exercises related to the discussion at hand. These exercises are not designed to be prize winning problems, but instead to be thought provoking. Wherever possible the problems are forward minded, stating problems that will be answered in subsequent chapters. The reader is encouraged to finish the exercises as they appear to get a better understanding of the subject material.

That being said, the problems are designed to affirm knowledge of a particular subject matter. Students in particular are encouraged to verify they can answer the problems correctly before moving on.

Similar to the exercises of [1, pp. ix] these exercises are given a scoring system based on the difficulty of the problem. However, unlike [1] the problems do not get nearly as hard. The scoring of these exercises ranges from one (the easiest) to five (the hardest). The following table sumarizes the scoring system used.

⁸Except where explicitly noted.

[1]	An easy problem that should only take the reader a manner of
' '	minutes to solve. Usually does not involve much computer time
	to solve.
[2]	An easy problem that involves a marginal amount of computer
	time usage. Usually requires a program to be written to
	solve the problem.
[3]	A moderately hard problem that requires a non-trivial amount
	of work. Usually involves trivial research and development of
	new theory from the perspective of a student.
[4]	A moderately hard problem that involves a non-trivial amount
	of work and research, the solution to which will demonstrate
	a higher mastery of the subject matter.
[5]	A hard problem that involves concepts that are difficult for a
	novice to solve. Solutions to these problems will demonstrate a
	complete mastery of the given subject.

Figure 1.2: Exercise Scoring System

Problems at the first level are meant to be simple questions that the reader can answer quickly without programming a solution or devising new theory. These problems are quick tests to see if the material is understood. Problems at the second level are also designed to be easy but will require a program or algorithm to be implemented to arrive at the answer. These two levels are essentially entry level questions.

Problems at the third level are meant to be a bit more difficult than the first two levels. The answer is often fairly obvious but arriving at an exacting solution requires some thought and skill. These problems will almost always involve devising a new algorithm or implementing a variation of another algorithm previously presented. Readers who can answer these questions will feel comfortable with the concepts behind the topic at hand.

Problems at the fourth level are meant to be similar to those of the level three questions except they will require additional research to be completed. The reader will most likely not know the answer right away, nor will the text provide the exact details of the answer until a subsequent chapter.

Problems at the fifth level are meant to be the hardest problems relative to all the other problems in the chapter. People who can correctly answer fifth level problems have a mastery of the subject matter at hand.

Often problems will be tied together. The purpose of this is to start a chain

of thought that will be discussed in future chapters. The reader is encouraged to answer the follow-up problems and try to draw the relevance of problems.

1.5 Introduction to LibTomMath

1.5.1 What is LibTomMath?

LibTomMath is a free and open source multiple precision integer library written entirely in portable ISO C. By portable it is meant that the library does not contain any code that is computer platform dependent or otherwise problematic to use on any given platform.

The library has been successfully tested under numerous operating systems including Unix⁹, MacOS, Windows, Linux, PalmOS and on standalone hardware such as the Gameboy Advance. The library is designed to contain enough functionality to be able to develop applications such as public key cryptosystems and still maintain a relatively small footprint.

1.5.2 Goals of LibTomMath

Libraries which obtain the most efficiency are rarely written in a high level programming language such as C. However, even though this library is written entirely in ISO C, considerable care has been taken to optimize the algorithm implementations within the library. Specifically the code has been written to work well with the GNU C Compiler (GCC) on both x86 and ARM processors. Wherever possible, highly efficient algorithms, such as Karatsuba multiplication, sliding window exponentiation and Montgomery reduction have been provided to make the library more efficient.

Even with the nearly optimal and specialized algorithms that have been included the Application Programing Interface (API) has been kept as simple as possible. Often generic place holder routines will make use of specialized algorithms automatically without the developer's specific attention. One such example is the generic multiplication algorithm **mp_mul()** which will automatically use Karatsuba, Toom-Cook, Comba or baseline multiplication based on the magnitude of the inputs and the configuration of the library.

Making LibTomMath as efficient as possible is not the only goal of the LibTomMath project. Ideally the library should be source compatible with another popular library which makes it more attractive for developers to use.

⁹All of these trademarks belong to their respective rightful owners.

In this case the MPI library was used as a API template for all the basic functions. MPI was chosen because it is another library that fits in the same niche as LibTomMath. Even though LibTomMath uses MPI as the template for the function names and argument passing conventions, it has been written from scratch by Tom St Denis.

The project is also meant to act as a learning tool for students, the logic being that no easy-to-follow "bignum" library exists which can be used to teach computer science students how to perform fast and reliable multiple precision integer arithmetic. To this end the source code has been given quite a few comments and algorithm discussion points.

1.6 Choice of LibTomMath

LibTomMath was chosen as the case study of this text not only because the author of both projects is one and the same but for more worthy reasons. Other libraries such as GMP [14], MPI [15], LIP [17] and OpenSSL [16] have multiple precision integer arithmetic routines but would not be ideal for this text for reasons that will be explained in the following sub-sections.

1.6.1 Code Base

The LibTomMath code base is all portable ISO C source code. This means that there are no platform dependent conditional segments of code littered throughout the source. This clean and uncluttered approach to the library means that a developer can more readily discern the true intent of a given section of source code without trying to keep track of what conditional code will be used.

The code base of LibTomMath is also well organized. Each function is in its own separate source code file which allows the reader to find a given function very quickly. On average there are about 76 lines of code per source file which makes the source very easily to follow. By comparison MPI and LIP are single file projects making code tracing very hard. GMP has many conditional code segments which also hinder tracing.

When compiled with GCC for the x86 processor and optimized for speed the entire library is approximately 66KiB¹⁰ which is fairly small compared to GMP (over 250KiB). LibTomMath is slightly larger than MPI (which compiles to about 50KiB) but LibTomMath is also much faster and more complete than MPI.

¹⁰The notation "KiB" means 2¹⁰ octets, similarly "MiB" means 2²⁰ octets.

1.6.2 API Simplicity

LibTomMath is designed after the MPI library and shares the API design. Quite often programs that use MPI will build with LibTomMath without change. The function names correlate directly to the action they perform. Almost all of the functions share the same parameter passing convention. The learning curve is fairly shallow with the API provided which is an extremely valuable benefit for the student and developer alike.

The LIP library is an example of a library with an API that is awkward to work with. LIP uses function names that are often "compressed" to illegible short hand. LibTomMath does not share this characteristic.

The GMP library also does not return error codes. Instead it uses a POSIX.1 [?] signal system where errors are signaled to the host application. This happens to be the fastest approach but definitely not the most versatile. In effect a math error (i.e. invalid input, heap error, etc) can cause a program to stop functioning which is definitely undersireable in many situations.

1.6.3 Optimizations

While LibTomMath is certainly not the fastest library (GMP often beats LibTom-Math by a factor of two) it does feature a set of optimal algorithms for tasks such as modular reduction, exponentiation, multiplication and squaring. GMP and LIP also feature such optimizations while MPI only uses baseline algorithms with no optimizations. GMP lacks a few of the additional modular reduction optimizations that LibTomMath features¹¹.

LibTomMath is almost always an order of magnitude faster than the MPI library at computationally expensive tasks such as modular exponentiation. In the grand scheme of "bignum" libraries LibTomMath is faster than the average library and usually slower than the best libraries such as GMP and OpenSSL by only a small factor.

1.6.4 Portability and Stability

LibTomMath will build "out of the box" on any platform equipped with a modern version of the GNU C Compiler (*GCC*). This means that without changes the library will build without configuration or setting up any variables. LIP and MPI will build "out of the box" as well but have numerous known bugs. Most

 $^{^{11}\}mathrm{At}$ the time of this writing GMP only had Barrett and Montgomery modular reduction algorithms.

notably the author of MPI has recently stopped working on his library and LIP has long since been discontinued.

GMP requires a configuration script to run and will not build out of the box. GMP and LibTomMath are still in active development and are very stable across a variety of platforms.

1.6.5 Choice

LibTomMath is a relatively compact, well documented, highly optimized and portable library which seems only natural for the case study of this text. Various source files from the LibTomMath project will be included within the text. However, the reader is encouraged to download their own copy of the library to actually be able to work with the library.

Chapter 2

Getting Started

2.1 Library Basics

The trick to writing any useful library of source code is to build a solid foundation and work outwards from it. First, a problem along with allowable solution parameters should be identified and analyzed. In this particular case the inability to accommodate multiple precision integers is the problem. Futhermore, the solution must be written as portable source code that is reasonably efficient across several different computer platforms.

After a foundation is formed the remainder of the library can be designed and implemented in a hierarchical fashion. That is, to implement the lowest level dependencies first and work towards the most abstract functions last. For example, before implementing a modular exponentiation algorithm one would implement a modular reduction algorithm. By building outwards from a base foundation instead of using a parallel design methodology the resulting project is highly modular. Being highly modular is a desirable property of any project as it often means the resulting product has a small footprint and updates are easy to perform.

Usually when I start a project I will begin with the header file. I define the data types I think I will need and prototype the initial functions that are not dependent on other functions (within the library). After I implement these base functions I prototype more dependent functions and implement them. The process repeats until I implement all of the functions I require. For example, in the case of LibTomMath I implemented functions such as mp_init() well before

I implemented mp_mul() and even further before I implemented mp_exptmod(). As an example as to why this design works note that the Karatsuba and Toom-Cook multipliers were written *after* the dependent function mp_exptmod() was written. Adding the new multiplication algorithms did not require changes to the mp_exptmod() function itself and lowered the total cost of ownership (so to speak) and of development for new algorithms. This methodology allows new algorithms to be tested in a complete framework with relative ease.




Figure 2.1: Design Flow of the First Few Original LibTomMath Functions.

Only after the majority of the functions were in place did I pursue a less hierarchical approach to auditing and optimizing the source code. For example, one day I may audit the multipliers and the next day the polynomial basis functions.

It only makes sense to begin the text with the preliminary data types and support algorithms required as well. This chapter discusses the core algorithms of the library which are the dependents for every other algorithm.

2.2 What is a Multiple Precision Integer?

Recall that most programming languages, in particular ISO C [18], only have fixed precision data types that on their own cannot be used to represent values

larger than their precision will allow. The purpose of multiple precision algorithms is to use fixed precision data types to create and manipulate multiple precision integers which may represent values that are very large.

As a well known analogy, school children are taught how to form numbers larger than nine by prepending more radix ten digits. In the decimal system the largest single digit value is 9. However, by concatenating digits together larger numbers may be represented. Newly prepended digits (to the left) are said to be in a different power of ten column. That is, the number 123 can be described as having a 1 in the hundreds column, 2 in the tens column and 3 in the ones column. Or more formally $123 = 1 \cdot 10^2 + 2 \cdot 10^1 + 3 \cdot 10^0$. Computer based multiple precision arithmetic is essentially the same concept. Larger integers are represented by adjoining fixed precision computer words with the exception that a different radix is used.

What most people probably do not think about explicitly are the various other attributes that describe a multiple precision integer. For example, the integer 154_{10} has two immediately obvious properties. First, the integer is positive, that is the sign of this particular integer is positive as opposed to negative. Second, the integer has three digits in its representation. There is an additional property that the integer posesses that does not concern pencil-and-paper arithmetic. The third property is how many digits placeholders are available to hold the integer.

The human analogy of this third property is ensuring there is enough space on the paper to write the integer. For example, if one starts writing a large number too far to the right on a piece of paper they will have to erase it and move left. Similarly, computer algorithms must maintain strict control over memory usage to ensure that the digits of an integer will not exceed the allowed boundaries. These three properties make up what is known as a multiple precision integer or mp_int for short.

2.2.1 The mp_int Structure

The mp_int structure is the ISO C based manifestation of what represents a multiple precision integer. The ISO C standard does not provide for any such data type but it does provide for making composite data types known as structures. The following is the structure definition used within LibTomMath.

```
typedef struct {
   int used, alloc, sign;
   mp_digit *dp;
```

} mp_int;

The mp_int structure can be broken down as follows.

- The used parameter denotes how many digits of the array dp contain the digits used to represent a given integer. The used count must be positive (or zero) and may not exceed the alloc count.
- 2. The alloc parameter denotes how many digits are available in the array to use by functions before it has to increase in size. When the used count of a result would exceed the alloc count all of the algorithms will automatically increase the size of the array to accommodate the precision of the result.
- 3. The pointer **dp** points to a dynamically allocated array of digits that represent the given multiple precision integer. It is padded with (**alloc used**) zero digits. The array is maintained in a least significant digit order. As a pencil and paper analogy the array is organized such that the right most digits are stored first starting at the location indexed by zero¹ in the array. For example, if **dp** contains $\{a, b, c, \ldots\}$ where $\mathbf{dp_0} = a$, $\mathbf{dp_1} = b$, $\mathbf{dp_2} = c$, ... then it would represent the integer $a + b\beta + c\beta^2 + \ldots$
- 4. The **sign** parameter denotes the sign as either zero/positive (**MP_ZPOS**) or negative (**MP_NEG**).

Valid mp_int Structures

Several rules are placed on the state of an mp_int structure and are assumed to be followed for reasons of efficiency. The only exceptions are when the structure is passed to initialization functions such as mp_init() and mp_init_copy().

- 1. The value of **alloc** may not be less than one. That is **dp** always points to a previously allocated array of digits.
- 2. The value of **used** may not exceed **alloc** and must be greater than or equal to zero.
- 3. The value of **used** implies the digit at index (used 1) of the **dp** array is non-zero. That is, leading zero digits in the most significant positions must be trimmed.

 $^{^{1}}$ In C all arrays begin at zero.

- (a) Digits in the **dp** array at and above the **used** location must be zero.
- 4. The value of **sign** must be **MP_ZPOS** if **used** is zero; this represents the mp_int value of zero.

2.3 Argument Passing

A convention of argument passing must be adopted early on in the development of any library. Making the function prototypes consistent will help eliminate many headaches in the future as the library grows to significant complexity. In LibTomMath the multiple precision integer functions accept parameters from left to right as pointers to mp_int structures. That means that the source (input) operands are placed on the left and the destination (output) on the right. Consider the following examples.

```
mp_mul(&a, &b, &c);  /* c = a * b */
mp_add(&a, &b, &a);  /* a = a + b */
mp_sqr(&a, &b);  /* b = a * a */
```

The left to right order is a fairly natural way to implement the functions since it lets the developer read aloud the functions and make sense of them. For example, the first function would read "multiply a and b and store in c".

Certain libraries (*LIP by Lenstra for instance*) accept parameters the other way around, to mimic the order of assignment expressions. That is, the destination (output) is on the left and arguments (inputs) are on the right. In truth, it is entirely a matter of preference. In the case of LibTomMath the convention from the MPI library has been adopted.

Another very useful design consideration, provided for in LibTomMath, is whether to allow argument sources to also be a destination. For example, the second example (mp_add) adds a to b and stores in a. This is an important feature to implement since it allows the calling functions to cut down on the number of variables it must maintain. However, to implement this feature specific care has to be given to ensure the destination is not modified before the source is fully read.

2.4 Return Values

A well implemented application, no matter what its purpose, should trap as many runtime errors as possible and return them to the caller. By catching runtime errors a library can be guaranteed to prevent undefined behaviour. However, the end developer can still manage to cause a library to crash. For example, by passing an invalid pointer an application may fault by dereferencing memory not owned by the application.

In the case of LibTomMath the only errors that are checked for are related to inappropriate inputs (division by zero for instance) and memory allocation errors. It will not check that the mp_int passed to any function is valid nor will it check pointers for validity. Any function that can cause a runtime error will return an error code as an **int** data type with one of the following values.

Value	Meaning
MP_OKAY	The function was successful
$\mathbf{MP}_{-}\mathbf{VAL}$	One of the input value(s) was invalid
MP_MEM	The function ran out of heap memory

When an error is detected within a function it should free any memory it allocated, often during the initialization of temporary mp_ints, and return as soon as possible. The goal is to leave the system in the same state it was when the function was called. Error checking with this style of API is fairly simple.

```
int err;
if ((err = mp_add(&a, &b, &c)) != MP_OKAY) {
   printf("Error: %s\n", mp_error_to_string(err));
   exit(EXIT_FAILURE);
}
```

The GMP [14] library uses C style *signals* to flag errors which is of questionable use. Not all errors are fatal and it was not deemed ideal by the author of LibTomMath to force developers to have signal handlers for such cases.

2.5 Initialization and Clearing

The logical starting point when actually writing multiple precision integer functions is the initialization and clearing of the mp_int structures. These two algorithms will be used by the majority of the higher level algorithms.

Given the basic mp_int structure an initialization routine must first allocate memory to hold the digits of the integer. Often it is optimal to allocate a sufficiently large pre-set number of digits even though the initial integer will represent zero. If only a single digit were allocated quite a few subsequent reallocations would occur when operations are performed on the integers. There is a tradeoff between how many default digits to allocate and how many reallocations are tolerable. Obviously allocating an excessive amount of digits initially will waste memory and become unmanageable.

If the memory for the digits has been successfully allocated then the rest of the members of the structure must be initialized. Since the initial state of an mp_int is to represent the zero integer, the allocated digits must be set to zero. The used count set to zero and sign set to MP_ZPOS.

2.5.1 Initializing an mp_int

An mp_int is said to be initialized if it is set to a valid, preferably default, state such that all of the members of the structure are set to valid values. The mp_init algorithm will perform such an action.

Algorithm mp_init.

Input. An mp_int a

Output. Allocate memory and initialize a to a known valid mp_int state.

- 1. Allocate memory for MP_PREC digits.
- 2. If the allocation failed return(MP_MEM)
- 3. for n from 0 to $MP_PREC 1$ do

 $3.1 \ a_n \leftarrow 0$

- 4. $a.sign \leftarrow MP_ZPOS$
- 5. $a.used \leftarrow 0$
- 6. $a.alloc \leftarrow MP_PREC$
- 7. Return $(MP_{-}OKAY)$

Figure 2.2: Algorithm mp_init

Algorithm mp_init. The MP_PREC name represents a constant² used to dictate the minimum precision of allocated mp_int integers. Ideally, it is at least equal to 32 since for most purposes that will be more than enough.

Memory for the default number of digits is allocated first. If the allocation fails the algorithm returns immediately with the **MP_MEM** error code. If

²Defined in the "tommath.h" header file within LibTomMath.

the allocation succeeds the remaining members of the mp_int structure must be initialized to reflect the default initial state.

The allocated digits are all set to zero (step three) to ensure they are in a known state. The **sign**, **used** and **alloc** are subsequently initialized to represent the zero integer. By step seven the algorithm returns a success code and the mp_int a has been successfully initialized to a valid state representing the integer zero.

Remark. This function introduces the idiosyncrasy that all iterative loops, commonly initiated with the "for" keyword, iterate incrementally when the "to" keyword is placed between two expressions. For example, "for a from b to c do" means that a subsequent expression (or body of expressions) are to be evaluated upto c-b times so long as $b \le c$. In each iteration the variable a is substituted for a new integer that lies inclusively between b and c. If b > c occurred the loop would not iterate. By contrast if the "downto" keyword were used in place of "to" the loop would iterate decrementally.

```
File: bn_mp_init.c
016
017
      /* init a new bigint */
018
      int mp_init (mp_int * a)
019
020
        /* allocate memory required and clear it */
021
        a->dp = OPT_CAST XCALLOC (sizeof (mp_digit), MP_PREC);
022
        if (a->dp == NULL) {
023
          return MP_MEM;
024
        }
025
026
        /* set the used to zero, allocated digits to the default precision
027
         * and sign to positive */
        a->used = 0;
028
029
        a->alloc = MP_PREC;
030
        a->sign = MP_ZPOS;
031
032
        return MP_OKAY;
033
      }
```

One immediate observation of this initialization function is that it does not return a pointer to a mp_int structure. It is assumed that the caller has already allocated memory for the mp_int structure, typically on the application stack. The call to mp_init() is used only to initialize the members of the structure to a known default state.

Before any of the other members of the structure are initialized memory from the application heap is allocated with the calloc() function (line @22,calloc@). The size of the allocated memory is large enough to hold **MP_PREC** mp_digit variables. The calloc() function is used instead³ of malloc() since digits have to be set to zero for the function to finish correctly. The **OPT_CAST** token is a macro definition which will turn into a cast from void * to mp_digit * for C++ compilers. It is not required for C compilers.

After the memory has been successfully allocated the remainder of the members are initialized (lines 28 through 30) to their respective default states. At this point the algorithm has succeeded and a success code is returned to the calling function.

If this function returns **MP_OKAY** it is safe to assume the mp_int structure has been properly initialized and is safe to use with other functions within the library.

2.5.2 Clearing an mp_int

When an mp_int is no longer required by the application, the memory that has been allocated for its digits must be returned to the application's memory pool with the mp_clear algorithm.

Algorithm **mp_clear**. **Input**. An mp_int *a* **Output**. The memory for *a* is freed for reuse.

- 1. If a has been previously freed then $return(MP_OKAY)$.
- 2. for n from 0 to a.used 1 do
 - $2.1 \ a_n \leftarrow 0$
- 3. Free the memory allocated for the digits of a.
- $4. \ a.used \leftarrow 0$
- 5. $a.alloc \leftarrow 0$
- 6. $a.sign \leftarrow MP_ZPOS$
- 7. Return (MP_OKAY) .

Figure 2.3: Algorithm mp_clear

 $^{^{3}}$ calloc() will allocate memory in the same manner as malloc() except that it also sets the contents to zero upon successfully allocating the memory.

Algorithm mp_clear. This algorithm releases the memory allocated for an mp_int back into the memory pool for reuse. It is designed such that a given mp_int structure can be cleared multiple times between initializations without attempting to free the memory twice⁴.

The first step determines if the mp_int structure has been marked as free already. If it has, the algorithm returns success immediately as no further actions are required. Otherwise, the algorithm will proceed to put the structure in a known empty and otherwise invalid state. First the digits of the mp_int are set to zero. The memory that has been allocated for the digits is then freed. The **used** and **alloc** counts are both set to zero and the **sign** set to **MP_ZPOS**. This known fixed state for cleared mp_int structures will make debuging easier for the end developer. That is, if they spot (via their debugger) an mp_int they are using that is in this state it will be obvious that they erroneously and prematurely cleared the mp_int structure.

Note that once an mp_int has been cleared the mp_int structure is no longer in a valid state for any other algorithm with the exception of algorithms mp_init, mp_init_copy, mp_init_size and mp_clear.

```
File: bn_mp_clear.c
016
      /* clear one (frees)
017
018
      biov
019
      mp_clear (mp_int * a)
020
        /* only do anything if a hasn't been freed previously */
021
022
        if (a->dp != NULL) {
023
           /* first zero the digits */
024
          memset (a->dp, 0, sizeof (mp_digit) * a->used);
025
026
           /* free ram */
027
          XFREE(a->dp);
028
           /* reset members to make debugging easier */
029
030
                    = NULL;
           a->dp
          a\rightarrow alloc = a\rightarrow used = 0:
031
          a->sign = MP_ZPOS;
032
033
        }
      }
034
```

 $^{^4\}mathrm{In}$ ISO C for example, calling free () twice on the same memory block causes undefinied behaviour.

The "if" statement (line 22) prevents the heap from being corrupted if a user double-frees an mp_int. This is because once the memory is freed the pointer is set to **NULL** (line 30).

Without the check, code that accidentally calls mp_clear twice for a given mp_int structure would try to free the memory allocated for the digits twice. This may cause some C libraries to signal a fault. By setting the pointer to **NULL** it helps debug code that may inadvertently free the mp_int before it is truly not needed, because attempts to reference digits should fail immediately. The allocated digits are set to zero before being freed (line 24). This is ideal for cryptographic situations where the integer that the mp_int represents might need to be kept a secret.

2.6 Maintenance Algorithms

The previous sections describes how to initialize and clear an mp_int structure. To further support operations that are to be performed on mp_int structures (such as addition and multiplication) the dependent algorithms must be able to augment the precision of an mp_int and initialize mp_ints with differing initial conditions.

These algorithms complete the set of low level algorithms required to work with mp_int structures in the higher level algorithms such as addition, multiplication and modular exponentiation.

2.6.1 Augmenting an mp_int's Precision

When storing a value in an mp_int structure, a sufficient number of digits must be available to accommodate the entire result of an operation without loss of precision. Quite often the size of the array given by the **alloc** member is large enough to simply increase the **used** digit count. However, when the size of the array is too small it must be re-sized appropriately to accommodate the result. The mp_grow algorithm will provide this functionality.

```
Algorithm mp_grow.

Input. An mp_int a and an integer b.

Output. a is expanded to accomodate b digits.

1. if a.alloc \ge b then return(MP\_OKAY)
2. u \leftarrow b \pmod{MP\_PREC}
3. v \leftarrow b + 2 \cdot MP\_PREC - u
4. Re-Allocate the array of digits a to size v
5. If the allocation failed then return(MP\_MEM).
6. for n from a.alloc to v - 1 do
6.1 a_n \leftarrow 0
7. a.alloc \leftarrow v
8. Return(MP\_OKAY)
```

Figure 2.4: Algorithm mp_grow

Algorithm mp_grow. It is ideal to prevent re-allocations from being performed if they are not required (step one). This is useful to prevent mp_ints from growing excessively in code that erroneously calls mp_grow.

The requested digit count is padded up to next multiple of MP_PREC plus an additional MP_PREC (steps two and three). This helps prevent many trivial reallocations that would grow an mp_int by trivially small values.

It is assumed that the reallocation (step four) leaves the lower *a.alloc* digits of the mp_int intact. This is much akin to how the *realloc* function from the standard C library works. Since the newly allocated digits are assumed to contain undefined values they are initially set to zero.

```
File: bn_mp_grow.c
016
017
      /* grow as required */
018
      int mp_grow (mp_int * a, int size)
019
020
        int
                i;
021
        mp_digit *tmp;
022
023
        /* if the alloc size is smaller alloc more ram */
024
        if (a->alloc < size) {
          /* ensure there are always at least MP_PREC digits extra on top */
025
          size += (MP_PREC * 2) - (size % MP_PREC);
026
027
```

```
028
          /* reallocate the array a->dp
029
030
           * We store the return in a temporary variable
031
           * in case the operation failed we don't want
032
           * to overwrite the dp member of a.
033
034
          tmp = OPT_CAST XREALLOC (a->dp, sizeof (mp_digit) * size);
035
          if (tmp == NULL) {
036
            /* reallocation failed but "a" is still valid [can be freed] */
037
            return MP_MEM;
038
039
040
          /* reallocation succeeded so set a->dp */
041
          a->dp = tmp;
042
043
          /* zero excess digits */
044
                    = a->alloc;
045
          a->alloc = size;
046
          for (; i < a->alloc; i++) {
047
            a \rightarrow dp[i] = 0;
048
049
050
        return MP_OKAY;
051
```

The first step is to see if we actually need to perform a re-allocation at all (line 24). If a reallocation must occur the digit count is padded upwards to help prevent many trivial reallocations (line 26). Next the reallocation is performed and the return of realloc() is stored in a temporary pointer named tmp (line 36). The return is stored in a temporary instead of a.dp to prevent the code from losing the original pointer in case the reallocation fails. Had the return been stored in a.dp instead there would be no way to reclaim the heap originally used.

If the reallocation fails the function will return $\mathbf{MP_MEM}$ (line 37), otherwise, the value of tmp is assigned to the pointer a.dp and the function continues. A simple for loop from line 46 to line 51 will zero all digits that were above the old **alloc** limit to make sure the integer is in a known state.

2.6.2 Initializing Variable Precision mp_ints

Algorithm mp_init_size.

Occasionally the number of digits required will be known in advance of an initialization, based on, for example, the size of input mp_ints to a given algorithm. The purpose of algorithm mp_init_size is similar to mp_init except that it will allocate at least a specified number of digits.

```
Input. An mp_int a and the requested number of digits b.

Output. a is initialized to hold at least b digits.

1. u \leftarrow b \pmod{MP\_PREC}
2. v \leftarrow b + 2 \cdot MP\_PREC - u
```

```
3. Allocate v digits.

4. for n from 0 to v-1 do

4.1 a_n \leftarrow 0

5. a.sign \leftarrow MP\_ZPOS

6. a.used \leftarrow 0

7. a.alloc \leftarrow v

8. Return(MP\_OKAY)
```

Figure 2.5: Algorithm mp_init_size

Algorithm mp_init_size. This algorithm will initialize an mp_int structure a like algorithm mp_init with the exception that the number of digits allocated can be controlled by the second input argument b. The input size is padded upwards so it is a multiple of MP_PREC plus an additional MP_PREC digits. This padding is used to prevent trivial allocations from becoming a bottleneck in the rest of the algorithms.

Like algorithm mp_init, the mp_int structure is initialized to a default state representing the integer zero. This particular algorithm is useful if it is known ahead of time the approximate size of the input. If the approximation is correct no further memory re-allocations are required to work with the mp_int.

```
File: bn_mp_init_size.c
016
017  /* init an mp_init for a given size */
018  int mp_init_size (mp_int * a, int size)
019  {
020    /* pad size so there are always extra digits */
021    size += (MP_PREC * 2) - (size % MP_PREC);
```

```
022
023
        /* alloc mem */
        a->dp = OPT_CAST XCALLOC (sizeof (mp_digit), size);
024
025
        if (a->dp == NULL) {
026
          return MP_MEM;
027
028
        a->used = 0:
029
        a->alloc = size:
030
        a->sign = MP_ZPOS;
031
032
        return MP_OKAY;
033
      }
```

The number of digits b requested is padded (line 21) by first augmenting it to the next multiple of MP_PREC and then adding MP_PREC to the result. If the memory can be successfully allocated the mp_int is placed in a default state representing the integer zero. Otherwise, the error code MP_MEM will be returned (line 26).

The digits are allocated and set to zero at the same time with the calloc() function (line @25,calloc@). The **used** count is set to zero, the **alloc** count set to the padded digit count and the **sign** flag set to **MP_ZPOS** to achieve a default valid mp_int state (lines 28, 29 and 30). If the function returns successfully then it is correct to assume that the mp_int structure is in a valid state for the remainder of the functions to work with.

2.6.3 Multiple Integer Initializations and Clearings

Occasionally a function will require a series of mp_int data types to be made available simultaneously. The purpose of algorithm mp_init_multi is to initialize a variable length array of mp_int structures in a single statement. It is essentially a shortcut to multiple initializations.

Algorithm **mp_init_multi**.

Input. Variable length array V_k of mp_int variables of length k.

Output. The array is initialized such that each mp_int of V_k is ready to use.

```
1. for n from 0 to k-1 do
1.1. Initialize the mp_int V_n (mp\_init)
1.2. If initialization failed then do
1.2.1. for j from 0 to n do
1.2.1.1. Free the mp_int V_j (mp\_clear)
1.2.2. Return(MP\_MEM)
2. Return(MP\_OKAY)
```

Figure 2.6: Algorithm mp_init_multi

Algorithm mp_init_multi. The algorithm will initialize the array of mp_int variables one at a time. If a runtime error has been detected (*step 1.2*) all of the previously initialized variables are cleared. The goal is an "all or nothing" initialization which allows for quick recovery from runtime errors.

```
File: bn_mp_init_multi.c
016
      #include <stdarg.h>
017
018
      int mp_init_multi(mp_int *mp, ...)
019
                                      /* Assume ok until proven otherwise */
020
          mp_err res = MP_OKAY;
                                      /* Number of ok inits */
021
          int n = 0;
          mp_int* cur_arg = mp;
022
023
          va_list args;
024
          va_start(args, mp);
                                      /* init args to next argument from caller */
025
026
          while (cur_arg != NULL) {
027
              if (mp_init(cur_arg) != MP_OKAY) {
028
                  /* Oops - error! Back-track and mp_clear what we already
029
                      succeeded in init-ing, then return error.
030
                  */
031
                  va_list clean_args;
032
033
                  /* end the current list */
034
                  va_end(args);
035
```

```
036
                   /* now start cleaning up */
037
                   cur_arg = mp;
038
                   va_start(clean_args, mp);
039
                   while (n--) {
040
                       mp_clear(cur_arg);
041
                       cur_arg = va_arg(clean_args, mp_int*);
042
043
                   va_end(clean_args);
044
                   res = MP_MEM;
045
                   break;
046
047
              n++;
048
              cur_arg = va_arg(args, mp_int*);
049
050
          va_end(args);
051
          return res;
                                       /* Assumed ok, if error flagged above. */
052
053
```

This function intializes a variable length list of mp_int structure pointers. However, instead of having the mp_int structures in an actual C array they are simply passed as arguments to the function. This function makes use of the "..." argument syntax of the C programming language. The list is terminated with a final **NULL** argument appended on the right.

The function uses the "stdarg.h" va functions to step portably through the arguments to the function. A count n of successfully initialized mp_int structures is maintained (line 47) such that if a failure does occur, the algorithm can backtrack and free the previously initialized structures (lines 27 to 46).

2.6.4 Clamping Excess Digits

When a function anticipates a result will be n digits it is simpler to assume this is true within the body of the function instead of checking during the computation. For example, a multiplication of a i digit number by a j digit produces a result of at most i+j digits. It is entirely possible that the result is i+j-1 though, with no final carry into the last position. However, suppose the destination had to be first expanded ($via\ mp_grow$) to accommodate i+j-1 digits than further expanded to accommodate the final carry. That would be a considerable waste of time since heap operations are relatively slow.

The ideal solution is to always assume the result is i+j and fix up the **used** count after the function terminates. This way a single heap operation (at most)

is required. However, if the result was not checked there would be an excess high order zero digit.

For example, suppose the product of two integers was $x_n = (0x_{n-1}x_{n-2}...x_0)_{\beta}$. The leading zero digit will not contribute to the precision of the result. In fact, through subsequent operations more leading zero digits would accumulate to the point the size of the integer would be prohibitive. As a result even though the precision is very low the representation is excessively large.

The mp_clamp algorithm is designed to solve this very problem. It will trim high-order zeros by decrementing the **used** count until a non-zero most significant digit is found. Also in this system, zero is considered to be a positive number which means that if the **used** count is decremented to zero, the sign must be set to **MP_ZPOS**.

```
Algorithm mp_clamp.

Input. An mp_int a
Output. Any excess leading zero digits of a are removed

1. while a.used > 0 and a_{a.used-1} = 0 do
1.1 a.used \leftarrow a.used - 1
2. if a.used = 0 then do
2.1 a.siqn \leftarrow MP\_ZPOS
```

Figure 2.7: Algorithm mp_clamp

Algorithm mp_clamp. As can be expected this algorithm is very simple. The loop on step one is expected to iterate only once or twice at the most. For example, this will happen in cases where there is not a carry to fill the last position. Step two fixes the sign for when all of the digits are zero to ensure that the mp_int is valid at all times.

```
File: bn_mp_clamp.c

016

017  /* trim unused digits

018  *

019  * This is used to ensure that leading zero digits are

020  * trimed and the leading "used" digit will be non-zero

021  * Typically very fast. Also fixes the sign if there

022  * are no more leading digits
```

```
023
       */
024
      void
      mp_clamp (mp_int * a)
025
026
027
        /* decrease used while the most significant digit is
028
         * zero.
029
         */
030
        while (a-)used > 0 && a-)dp[a-)used - 1] == 0) {
031
          --(a->used);
032
        }
033
        /* reset the sign flag if used == 0 */
034
        if (a->used == 0) {
035
          a->sign = MP_ZPOS;
036
037
        }
038
```

Note on line 27 how to test for the **used** count is made on the left of the && operator. In the C programming language the terms to && are evaluated left to right with a boolean short-circuit if any condition fails. This is important since if the **used** is zero the test on the right would fetch below the array. That is obviously undesirable. The parenthesis on line 30 is used to make sure the **used** count is decremented and not the pointer "a".

Exercises

- [1] Discuss the relevance of the **used** member of the mp_int structure.
- [1] Discuss the consequences of not using padding when performing allocations.
- [2] Estimate an ideal value for MP_PREC when performing 1024-bit RSA encryption when $\beta = 2^{28}$.
- [1] Discuss the relevance of the algorithm mp_clamp. What does it prevent?
- [1] Give an example of when the algorithm mp_init_copy might be useful.

Chapter 3

Basic Operations

3.1 Introduction

In the previous chapter a series of low level algorithms were established that dealt with initializing and maintaining mp_int structures. This chapter will discuss another set of seemingly non-algebraic algorithms which will form the low level basis of the entire library. While these algorithm are relatively trivial it is important to understand how they work before proceeding since these algorithms will be used almost intrinsically in the following chapters.

The algorithms in this chapter deal primarily with more "programmer" related tasks such as creating copies of mp_int structures, assigning small values to mp_int structures and comparisons of the values mp_int structures represent.

3.2 Assigning Values to mp_int Structures

3.2.1 Copying an mp_int

Assigning the value that a given mp_int structure represents to another mp_int structure shall be known as making a copy for the purposes of this text. The copy of the mp_int will be a separate entity that represents the same value as the mp_int it was copied from. The mp_copy algorithm provides this functionality.

```
Algorithm mp_copy.

Input. An mp_int a and b.

Output. Store a copy of a in b.

1. If b.alloc < a.used then grow b to a.used digits. (mp\_grow)
2. for n from 0 to a.used - 1 do
2.1 b_n \leftarrow a_n
3. for n from a.used to b.used - 1 do
3.1 b_n \leftarrow 0
4. b.used \leftarrow a.used
5. b.sign \leftarrow a.sign
6. return(MP\_OKAY)
```

Figure 3.1: Algorithm mp_copy

Algorithm mp_copy. This algorithm copies the mp_int a such that upon successful termination of the algorithm the mp_int b will represent the same integer as the mp_int a. The mp_int b shall be a complete and distinct copy of the mp_int a meaning that the mp_int a can be modified and it shall not affect the value of the mp_int b.

If b does not have enough room for the digits of a it must first have its precision augmented via the mp_grow algorithm. The digits of a are copied over the digits of b and any excess digits of b are set to zero (step two and three). The **used** and **sign** members of a are finally copied over the respective members of b.

Remark. This algorithm also introduces a new idiosyncrasy that will be used throughout the rest of the text. The error return codes of other algorithms are not explicitly checked in the pseudo-code presented. For example, in step one of the mp_copy algorithm the return of mp_grow is not explicitly checked to ensure it succeeded. Text space is limited so it is assumed that if a algorithm fails it will clear all temporarily allocated mp_ints and return the error code itself. However, the C code presented will demonstrate all of the error handling logic required to implement the pseudo-code.

```
File: bn_mp_copy.c
016
017    /* copy, b = a */
018    int
019    mp_copy (mp_int * a, mp_int * b)
```

```
020
021
        int
                res, n;
022
023
        /* if dst == src do nothing */
024
        if (a == b) {
025
          return MP_OKAY;
026
        }
027
028
        /* grow dest */
029
        if (b->alloc < a->used) \{
030
           if ((res = mp_grow (b, a->used)) != MP_OKAY) {
031
              return res;
032
           }
033
        }
034
035
        /* zero b and copy the parameters over */
036
037
          register mp_digit *tmpa, *tmpb;
038
039
          /* pointer aliases */
040
041
          /* source */
042
          tmpa = a->dp;
043
044
          /* destination */
045
          tmpb = b->dp;
046
047
          /* copy all the digits */
048
          for (n = 0; n < a->used; n++) {
049
            *tmpb++ = *tmpa++;
050
051
052
          /* clear high digits */
053
          for (; n < b->used; n++) {
            *tmpb++ = 0;
054
055
056
        }
057
058
        /* copy used count and sign */
059
        b->used = a->used;
060
        b->sign = a->sign;
061
        return MP_OKAY;
```

```
062 }
```

Occasionally a dependent algorithm may copy an mp_int effectively into itself such as when the input and output mp_int structures passed to a function are one and the same. For this case it is optimal to return immediately without copying digits (line 24).

The mp_int b must have enough digits to accommodate the used digits of the mp_int a. If b.alloc is less than a.used the algorithm mp_grow is used to augment the precision of b (lines 29 to 33). In order to simplify the inner loop that copies the digits from a to b, two aliases tmpa and tmpb point directly at the digits of the mp_ints a and b respectively. These aliases (lines 42 and 45) allow the compiler to access the digits without first dereferencing the mp_int pointers and then subsequently the pointer to the digits.

After the aliases are established the digits from a are copied into b (lines 48 to 50) and then the excess digits of b are set to zero (lines 53 to 55). Both "for" loops make use of the pointer aliases and in fact the alias for b is carried through into the second "for" loop to clear the excess digits. This optimization allows the alias to stay in a machine register fairly easy between the two loops.

Remarks. The use of pointer aliases is an implementation methodology first introduced in this function that will be used considerably in other functions. Technically, a pointer alias is simply a short hand alias used to lower the number of pointer dereferencing operations required to access data. For example, a for loop may resemble

```
for (x = 0; x < 100; x++) {
    a->num[4]->dp[x] = 0;
}
This could be re-written using aliases as
mp_digit *tmpa;
```

```
mp_digit *tmpa;
a = a->num[4]->dp;
for (x = 0; x < 100; x++) {
    *a++ = 0;
}</pre>
```

In this case an alias is used to access the array of digits within an mp_int structure directly. It may seem that a pointer alias is strictly not required as a compiler may optimize out the redundant pointer operations. However, there are two dominant reasons to use aliases.

The first reason is that most compilers will not effectively optimize pointer arithmetic. For example, some optimizations may work for the Microsoft Visual C++ compiler (MSVC) and not for the GNU C Compiler (GCC). Also some optimizations may work for GCC and not MSVC. As such it is ideal to find a common ground for as many compilers as possible. Pointer aliases optimize the code considerably before the compiler even reads the source code which means the end compiled code stands a better chance of being faster.

The second reason is that pointer aliases often can make an algorithm simpler to read. Consider the first "for" loop of the function mp_copy() re-written to not use pointer aliases.

```
/* copy all the digits */
for (n = 0; n < a->used; n++) {
  b->dp[n] = a->dp[n];
}
```

Whether this code is harder to read depends strongly on the individual. However, it is quantifiably slightly more complicated as there are four variables within the statement instead of just two.

Nested Statements

Another commonly used technique in the source routines is that certain sections of code are nested. This is used in particular with the pointer aliases to highlight code phases. For example, a Comba multiplier (discussed in chapter six) will typically have three different phases. First the temporaries are initialized, then the columns calculated and finally the carries are propagated. In this example the middle column production phase will typically be nested as it uses temporary variables and aliases the most.

The nesting also simplies the source code as variables that are nested are only valid for their scope. As a result the various temporary variables required do not propagate into other sections of code.

3.2.2 Creating a Clone

Another common operation is to make a local temporary copy of an mp_int argument. To initialize an mp_int and then copy another existing mp_int into the newly intialized mp_int will be known as creating a clone. This is useful within functions that need to modify an argument but do not wish to actually

modify the original copy. The mp_init_copy algorithm has been designed to help perform this task.

```
Algorithm mp_init_copy.
Input. An mp_int a and b
Output. a is initialized to be a copy of b.

1. Init a. (mp_init)
2. Copy b to a. (mp_copy)
```

Figure 3.2: Algorithm mp_init_copy

3. Return the status of the copy operation.

Algorithm mp_init_copy. This algorithm will initialize an mp_int variable and copy another previously initialized mp_int variable into it. As such this algorithm will perform two operations in one step.

```
File: bn_mp_init_copy.c
016
017
      /* creates "a" then copies b into it */
      int mp_init_copy (mp_int * a, mp_int * b)
018
019
020
        int
                 res;
021
        if ((res = mp_init (a)) != MP_OKAY) {
022
023
          return res;
024
025
        return mp_copy (b, a);
026
      }
```

This will initialize **a** and make it a verbatim copy of the contents of **b**. Note that **a** will have its own memory allocated which means that **b** may be cleared after the call and **a** will be left intact.

3.3 Zeroing an Integer

Reseting an mp_int to the default state is a common step in many algorithms. The mp_zero algorithm will be the algorithm used to perform this task.

Algorithm mp_zero. This algorithm simply resets a mp_int to the default state.

```
Algorithm mp_zero.

Input. An mp_int a
Output. Zero the contents of a

1. a.used \leftarrow 0
2. a.sign \leftarrow \text{MP}\_\text{ZPOS}
3. for n from 0 to a.alloc - 1 do
3.1 \ a_n \leftarrow 0
```

Figure 3.3: Algorithm mp_zero

After the function is completed, all of the digits are zeroed, the **used** count is zeroed and the **sign** variable is set to **MP_ZPOS**.

3.4 Sign Manipulation

3.4.1 Absolute Value

With the mp_int representation of an integer, calculating the absolute value is trivial. The mp_abs algorithm will compute the absolute value of an mp_int.

```
Algorithm mp_abs.

Input. An mp_int a
Output. Computes b = |a|

1. Copy a to b. (mp\_copy)
2. If the copy failed return (MP\_MEM).
3. b.sign \leftarrow MP\_ZPOS
4. Return (MP\_OKAY)
```

Figure 3.4: Algorithm mp_abs

Algorithm mp_abs. This algorithm computes the absolute of an mp_int input. First it copies a over b. This is an example of an algorithm where the check in mp_copy that determines if the source and destination are equal proves useful. This allows, for instance, the developer to pass the same mp_int as the source and destination to this function without addition logic to handle it.

```
File: bn_mp_abs.c
016
017
      /* b = |a|
018
019
       * Simple function copies the input and fixes the sign to positive
020
       */
021
      int
      mp_abs (mp_int * a, mp_int * b)
022
023
024
        int
                res;
025
        /* copy a to b */
026
027
        if (a != b) {
028
           if ((res = mp_copy (a, b)) != MP_OKAY) {
029
             return res;
030
           }
031
        }
032
033
        /* force the sign of b to positive */
034
        b->sign = MP_ZPOS;
035
036
        return MP_OKAY;
037
      }
```

3.4.2 Integer Negation

With the mp_int representation of an integer, calculating the negation is also trivial. The mp_neg algorithm will compute the negative of an mp_int input.

```
Algorithm mp_neg.

Input. An mp_int a
Output. Computes b = -a

1. Copy a to b. (mp\_copy)
2. If the copy failed return (MP\_MEM).
3. If a.used = 0 then return (MP\_OKAY).
4. If a.sign = MP\_ZPOS then do
4.1 b.sign = MP\_NEG.
5. else do
5.1 b.sign = MP\_ZPOS.
6. Return (MP\_OKAY)
```

Figure 3.5: Algorithm mp_neg

Algorithm mp_neg. This algorithm computes the negation of an input. First it copies a over b. If a has no used digits then the algorithm returns immediately. Otherwise it flips the sign flag and stores the result in b. Note that if a had no digits then it must be positive by definition. Had step three been omitted then the algorithm would return zero as negative.

```
File: bn_mp_neg.c
016
017
      /* b = -a */
      int mp_neg (mp_int * a, mp_int * b)
018
019
020
        int
                 res;
021
        if ((res = mp_copy (a, b)) != MP_OKAY) {
022
          return res;
023
        }
024
        if (mp_iszero(b) != 1) {
025
           b->sign = (a->sign == MP_ZPOS) ? MP_NEG : MP_ZPOS;
        }
026
027
        return MP_OKAY;
028
      }
```

3.5 Small Constants

3.5.1 Setting Small Constants

Often a mp_int must be set to a relatively small value such as 1 or 2. For these cases the mp_set algorithm is useful.

```
Algorithm mp_set.

Input. An mp_int a and a digit b

Output. Make a equivalent to b

1. Zero a (mp\_zero).
2. a_0 \leftarrow b (mod \beta)
3. a.used \leftarrow \begin{cases} 1 & \text{if } a_0 > 0 \\ 0 & \text{if } a_0 = 0 \end{cases}
```

Figure 3.6: Algorithm mp_set

Algorithm mp_set. This algorithm sets a mp_int to a small single digit value. Step number 1 ensures that the integer is reset to the default state. The single digit is set $(modulo \ \beta)$ and the used count is adjusted accordingly.

```
File: bn_mp_set.c
016
017    /* set to a digit */
018    void mp_set (mp_int * a, mp_digit b)
019    {
020         mp_zero (a);
021         a->dp[0] = b & MP_MASK;
022         a->used = (a->dp[0] != 0) ? 1 : 0;
023    }
```

Line 20 calls mp_zero() to clear the mp_int and reset the sign. Line 21 copies the digit into the least significant location. Note the usage of a new constant $\mathbf{MP_MASK}$. This constant is used to quickly reduce an integer modulo β . Since β is of the form 2^k for any suitable k it suffices to perform a binary AND with $MP_MASK = 2^k - 1$ to perform the reduction. Finally line 22 will set the used member with respect to the digit actually set. This function will always make the integer positive.

One important limitation of this function is that it will only set one digit. The size of a digit is not fixed, meaning source that uses this function should take that into account. Only trivially small constants can be set using this function.

3.5.2 Setting Large Constants

To overcome the limitations of the mp_set algorithm the mp_set_int algorithm is ideal. It accepts a "long" data type as input and will always treat it as a 32-bit integer.

Algorithm **mp_set_int**.

```
Input. An mp_int a and a "long" integer b
Output. Make a equivalent to b

1. Zero a (mp\_zero)
2. for n from 0 to 7 do
2.1 a \leftarrow a \cdot 16 (mp\_mul2d)
2.2 u \leftarrow \lfloor b/2^{4(7-n)} \rfloor (mod 16)
2.3 a_0 \leftarrow a_0 + u
2.4 a.used \leftarrow a.used + 1
3. Clamp excess used digits (mp\_clamp)
```

Figure 3.7: Algorithm mp_set_int

Algorithm mp_set_int. The algorithm performs eight iterations of a simple loop where in each iteration four bits from the source are added to the mp_int. Step 2.1 will multiply the current result by sixteen making room for four more bits in the less significant positions. In step 2.2 the next four bits from the source are extracted and are added to the mp_int. The used digit count is incremented to reflect the addition. The used digit counter is incremented since if any of the leading digits were zero the mp_int would have zero digits used and the newly added four bits would be ignored.

Excess zero digits are trimmed in steps 2.1 and 3 by using higher level algorithms mp_mul2d and mp_clamp.

```
File: bn_mp_set_int.c
016
017  /* set a 32-bit const */
018  int mp_set_int (mp_int * a, unsigned long b)
019  {
```

```
020
        int
                 x, res;
021
022
        mp_zero (a);
023
024
        /* set four bits at a time */
        for (x = 0; x < 8; x++) {
025
026
          /* shift the number up four bits */
          if ((res = mp_mul_2d (a, 4, a)) != MP_OKAY) {
027
             return res;
028
029
          }
030
          /* OR in the top four bits of the source */
0.31
032
          a \rightarrow dp[0] = (b >> 28) & 15;
033
034
          /* shift the source up to the next four bits */
035
          b <<= 4;
036
037
          /* ensure that digits are not clamped off */
038
          a->used += 1;
039
040
        mp_clamp (a);
        return MP_OKAY;
041
042
```

This function sets four bits of the number at a time to handle all practical **DIGIT_BIT** sizes. The weird addition on line 38 ensures that the newly added in bits are added to the number of digits. While it may not seem obvious as to why the digit counter does not grow exceedingly large it is because of the shift on line 27 as well as the call to mp_clamp() on line 40. Both functions will clamp excess leading digits which keeps the number of used digits low.

3.6 Comparisons

3.6.1 Unsigned Comparisions

Comparing a multiple precision integer is performed with the exact same algorithm used to compare two decimal numbers. For example, to compare 1,234 to 1,264 the digits are extracted by their positions. That is we compare $1 \cdot 10^3 + 2 \cdot 10^2 + 3 \cdot 10^1 + 4 \cdot 10^0$ to $1 \cdot 10^3 + 2 \cdot 10^2 + 6 \cdot 10^1 + 4 \cdot 10^0$ by comparing single digits at a time starting with the highest magnitude positions.

If any leading digit of one integer is greater than a digit in the same position of another integer then obviously it must be greater.

The first comparision routine that will be developed is the unsigned magnitude compare which will perform a comparison based on the digits of two mp_int variables alone. It will ignore the sign of the two inputs. Such a function is useful when an absolute comparison is required or if the signs are known to agree in advance.

To facilitate working with the results of the comparison functions three constants are required.

Constant	Meaning
MP_GT	Greater Than
MP_EQ	Equal To
MP_LT	Less Than

Figure 3.8: Comparison Return Codes

```
Algorithm \mathbf{mp\_cmp\_mag}.

\mathbf{Input}. Two \mathbf{mp\_ints}\ a and b.

\mathbf{Output}. Unsigned comparison results (a to the left of b).
```

- 1. If a.used > b.used then return (MP_GT)
- 2. If a.used < b.used then $return(MP_LT)$
- 3. for n from a.used 1 to 0 do
 - 3.1 if $a_n > b_n$ then return (MP_-GT)
 - 3.2 if $a_n < b_n$ then return (MP_LT)
- 4. Return (MP_EQ)

Figure 3.9: Algorithm mp_cmp_mag

Algorithm mp_cmp_mag. By saying "a to the left of b" it is meant that the comparison is with respect to a, that is if a is greater than b it will return $\mathbf{MP_GT}$ and similar with respect to when a=b and a < b. The first two steps compare the number of digits used in both a and b. Obviously if the digit counts differ there would be an imaginary zero digit in the smaller number where the leading digit of the larger number is. If both have the same number

of digits than the actual digits themselves must be compared starting at the leading digit.

By step three both inputs must have the same number of digits so its safe to start from either a.used-1 or b.used-1 and count down to the zero'th digit. If after all of the digits have been compared, no difference is found, the algorithm returns $\mathbf{MP}.\mathbf{EQ}$.

```
File: bn_mp_cmp_mag.c
016
017
      /* compare maginitude of two ints (unsigned) */
018
      int mp_cmp_mag (mp_int * a, mp_int * b)
019
020
        int
                n;
021
        mp_digit *tmpa, *tmpb;
022
023
        /* compare based on # of non-zero digits */
024
        if (a-)used > b-)used) {
025
          return MP_GT;
026
027
028
        if (a->used < b->used) {
029
          return MP_LT;
030
031
032
        /* alias for a */
        tmpa = a->dp + (a->used - 1);
033
034
035
        /* alias for b */
036
        tmpb = b->dp + (a->used - 1);
037
038
        /* compare based on digits */
039
        for (n = 0; n < a-)used; ++n, --tmpa, --tmpb) {
040
          if (*tmpa > *tmpb) {
041
            return MP_GT;
042
          }
043
          if (*tmpa < *tmpb) {</pre>
044
045
            return MP_LT;
046
        }
047
048
        return MP_EQ;
049
      }
```

The two if statements on lines 24 and 28 compare the number of digits in the two inputs. These two are performed before all of the digits are compared since it is a very cheap test to perform and can potentially save considerable time. The implementation given is also not valid without those two statements. b.alloc may be smaller than a.used, meaning that undefined values will be read from b past the end of the array of digits.

3.6.2 Signed Comparisons

Comparing with sign considerations is also fairly critical in several routines (division for example). Based on an unsigned magnitude comparison a trivial signed comparison algorithm can be written.

```
Algorithm mp_cmp.
Input. Two mp_ints a and b
Output. Signed Comparison Results (a to the left of b)

1. if a.sign = MP_NEG and b.sign = MP_ZPOS then return(MP_LT)
2. if a.sign = MP_ZPOS and b.sign = MP_NEG then return(MP_GT)
3. if a.sign = MP_NEG then
3.1 Return the unsigned comparison of b and a (mp_cmp_mag)
4 Otherwise
4.1 Return the unsigned comparison of a and b
```

Figure 3.10: Algorithm mp_cmp

Algorithm mp_cmp. The first two steps compare the signs of the two inputs. If the signs do not agree then it can return right away with the appropriate comparison code. When the signs are equal the digits of the inputs must be compared to determine the correct result. In step three the unsigned comparision flips the order of the arguments since they are both negative. For instance, if -a > -b then |a| < |b|. Step number four will compare the two when they are both positive.

```
File: bn_mp_cmp.c
016
017  /* compare two ints (signed)*/
018  int
019  mp_cmp (mp_int * a, mp_int * b)
```

```
020
021
        /* compare based on sign */
        if (a->sign != b->sign) {
022
023
           if (a->sign == MP_NEG) {
024
              return MP_LT;
025
           } else {
026
              return MP_GT;
027
        }
028
029
        /* compare digits */
030
        if (a->sign == MP_NEG) {
031
032
           /* if negative compare opposite direction */
033
           return mp_cmp_mag(b, a);
034
        } else {
035
           return mp_cmp_mag(a, b);
036
037
      }
```

The two if statements on lines 22 and 23 perform the initial sign comparison. If the signs are not the equal then which ever has the positive sign is larger. At line 31, the inputs are compared based on magnitudes. If the signs were both negative then the unsigned comparison is performed in the opposite direction (line 33). Otherwise, the signs are assumed to be both positive and a forward direction unsigned comparison is performed.

Exercises

- [2] Modify algorithm mp_set_int to accept as input a variable length array of bits.
- [3] Give the probability that algorithm mp_cmp_mag will have to compare k digits of two random digits (of equal magnitude) before a difference is found.
- [1] Suggest a simple method to speed up the implementation of mp_cmp_mag based on the observations made in the previous problem.

Chapter 4

Basic Arithmetic

4.1 Introduction

At this point algorithms for initialization, clearing, zeroing, copying, comparing and setting small constants have been established. The next logical set of algorithms to develop are addition, subtraction and digit shifting algorithms. These algorithms make use of the lower level algorithms and are the cruicial building block for the multiplication algorithms. It is very important that these algorithms are highly optimized. On their own they are simple O(n) algorithms but they can be called from higher level algorithms which easily places them at $O(n^2)$ or even $O(n^3)$ work levels.

All of the algorithms within this chapter make use of the logical bit shift operations denoted by << and >> for left and right logical shifts respectively. A logical shift is analogous to sliding the decimal point of radix-10 representations. For example, the real number 0.9345 is equivalent to 93.45% which is found by sliding the the decimal two places to the right (multiplying by $\beta^2 = 10^2$). Algebraically a binary logical shift is equivalent to a division or multiplication by a power of two. For example, $a << k = a \cdot 2^k$ while $a >> k = |a/2^k|$.

One significant difference between a logical shift and the way decimals are shifted is that digits below the zero'th position are removed from the number. For example, consider $1101_2 >> 1$ using decimal notation this would produce 110.1_2 . However, with a logical shift the result is 110_2 .

4.2 Addition and Subtraction

In common twos complement fixed precision arithmetic negative numbers are easily represented by subtraction from the modulus. For example, with 32-bit integers $a-b \pmod{2^{32}}$ is the same as $a+(2^{32}-b) \pmod{2^{32}}$ since $2^{32}\equiv 0 \pmod{2^{32}}$. As a result subtraction can be performed with a trivial series of logical operations and an addition.

However, in multiple precision arithmetic negative numbers are not represented in the same way. Instead a sign flag is used to keep track of the sign of the integer. As a result signed addition and subtraction are actually implemented as conditional usage of lower level addition or subtraction algorithms with the sign fixed up appropriately.

The lower level algorithms will add or subtract integers without regard to the sign flag. That is they will add or subtract the magnitude of the integers respectively.

4.2.1 Low Level Addition

An unsigned addition of multiple precision integers is performed with the same long-hand algorithm used to add decimal numbers. That is to add the trailing digits first and propagate the resulting carry upwards. Since this is a lower level algorithm the name will have a "s_" prefix. Historically that convention stems from the MPI library where "s_" stood for static functions that were hidden from the developer entirely.

```
Algorithm s_mp_add.
Input. Two mp_ints a and b
Output. The unsigned addition c = |a| + |b|.
1. if a.used > b.used then
  1.1 \ min \leftarrow b.used
  1.2 \ max \leftarrow a.used
  1.3 \ x \leftarrow a
2. else
  2.1 \ min \leftarrow a.used
  2.2 \ max \leftarrow b.used
  2.3 \ x \leftarrow b
3. If c.alloc < max + 1 then grow c to hold at least max + 1 digits (mp\_qrow)
4. oldused \leftarrow c.used
5. c.used \leftarrow max + 1
6. u \leftarrow 0
7. for n from 0 to min - 1 do
  7.1 c_n \leftarrow a_n + b_n + u
  7.2 \ u \leftarrow c_n >> lg(\beta)
  7.3 \ c_n \leftarrow c_n \pmod{\beta}
8. if min \neq max then do
  8.1 for n from min to max - 1 do
     8.1.1 c_n \leftarrow x_n + u
     8.1.2 \ u \leftarrow c_n >> lg(\beta)
     8.1.3 c_n \leftarrow c_n \pmod{\beta}
9. c_{max} \leftarrow u
10. if olduse > max then
   10.1 for n from max + 1 to oldused - 1 do
     10.1.1 \ c_n \leftarrow 0
11. Clamp excess digits in c. (mp\_clamp)
12. Return(MP\_OKAY)
```

Figure 4.1: Algorithm s_mp_add

Algorithm s_mp_add. This algorithm is loosely based on algorithm 14.7 of HAC [2, pp. 594] but has been extended to allow the inputs to have different magnitudes. Coincidentally the description of algorithm A in Knuth [1, pp. 266] shares the same deficiency as the algorithm from [2]. Even the MIX pseudo machine code presented by Knuth [1, pp. 266-267] is incapable of handling inputs which are of different magnitudes.

The first thing that has to be accomplished is to sort out which of the two

inputs is the largest. The addition logic will simply add all of the smallest input to the largest input and store that first part of the result in the destination. Then it will apply a simpler addition loop to excess digits of the larger input.

The first two steps will handle sorting the inputs such that min and max hold the digit counts of the two inputs. The variable x will be an mp_int alias for the largest input or the second input b if they have the same number of digits. After the inputs are sorted the destination c is grown as required to accommodate the sum of the two inputs. The original **used** count of c is copied and set to the new used count.

At this point the first addition loop will go through as many digit positions that both inputs have. The carry variable μ is set to zero outside the loop. Inside the loop an "addition" step requires three statements to produce one digit of the summand. First two digits from a and b are added together along with the carry μ . The carry of this step is extracted and stored in μ and finally the digit of the result c_n is truncated within the range $0 \le c_n < \beta$.

Now all of the digit positions that both inputs have in common have been exhausted. If $min \neq max$ then x is an alias for one of the inputs that has more digits. A simplified addition loop is then used to essentially copy the remaining digits and the carry to the destination.

The final carry is stored in c_{max} and digits above max upto oldused are zeroed which completes the addition.

```
File: bn_s_mp_add.c
016
017
      /* low level addition, based on HAC pp.594, Algorithm 14.7 */
018
019
      s_mp_add (mp_int * a, mp_int * b, mp_int * c)
020
021
        mp_int *x;
022
                olduse, res, min, max;
023
024
        /* find sizes, we let |a| <= |b| which means we have to sort
025
         * them. "x" will point to the input with the most digits
026
         */
027
        if (a-)used > b-)used) {
          min = b->used;
028
          max = a->used;
029
030
          x = a;
031
        } else {
032
          min = a->used;
033
          max = b->used;
```

```
034
          x = b;
035
036
037
        /* init result */
038
        if (c->alloc < max + 1) {
039
          if ((res = mp_grow (c, max + 1)) != MP_OKAY) {
040
            return res;
041
          }
042
        }
043
044
        /* get old used digit count and set new one */
045
        olduse = c->used;
046
        c->used = max + 1;
047
048
049
          register mp_digit u, *tmpa, *tmpb, *tmpc;
050
          register int i;
051
052
          /* alias for digit pointers */
053
054
          /* first input */
055
          tmpa = a->dp;
056
057
          /* second input */
058
          tmpb = b->dp;
059
060
          /* destination */
061
          tmpc = c->dp;
062
063
          /* zero the carry */
          u = 0;
064
          for (i = 0; i < min; i++) {
065
066
            /* Compute the sum at one digit, T[i] = A[i] + B[i] + U */
067
            *tmpc = *tmpa++ + *tmpb++ + u;
068
069
            /* U = carry bit of T[i] */
070
            u = *tmpc >> ((mp_digit)DIGIT_BIT);
071
072
            /* take away carry bit from T[i] */
073
            *tmpc++ &= MP_MASK;
074
          }
075
```

```
076
          /* now copy higher words if any, that is in A+B
           * if A or B has more digits add those in
077
           */
078
079
          if (min != max) {
080
            for (; i < max; i++) {
081
              /* T[i] = X[i] + U */
082
              *tmpc = x->dp[i] + u;
083
              /* U = carry bit of T[i] */
084
085
              u = *tmpc >> ((mp_digit)DIGIT_BIT);
086
087
              /* take away carry bit from T[i] */
088
              *tmpc++ &= MP_MASK;
089
090
          }
091
092
          /* add carry */
093
          *tmpc++ = u;
094
095
          /* clear digits above oldused */
096
          for (i = c->used; i < olduse; i++) {
097
            *tmpc++ = 0;
098
        }
099
100
101
        mp_clamp (c);
102
        return MP_OKAY;
103
```

Lines 27 to 35 perform the initial sorting of the inputs and determine the min and max variables. Note that x is a pointer to a mp_int assigned to the largest input, in effect it is a local alias. Lines 37 to 42 ensure that the destination is grown to accommodate the result of the addition.

Similar to the implementation of mp_copy this function uses the braced code and local aliases coding style. The three aliases that are on lines 55, 58 and 61 represent the two inputs and destination variables respectively. These aliases are used to ensure the compiler does not have to dereference a, b or c (respectively) to access the digits of the respective mp_int.

The initial carry u is cleared on line 64, note that u is of type mp_digit which ensures type compatibility within the implementation. The initial addition loop begins on line 65 and ends on line 74. Similarly the conditional addition loop

begins on line 80 and ends on line 90. The addition is finished with the final carry being stored in tmpc on line 93. Note the "++" operator on the same line. After line 93 tmpc will point to the c.used'th digit of the mp_int c. This is useful for the next loop on lines 96 to 99 which set any old upper digits to zero.

4.2.2 Low Level Subtraction

The low level unsigned subtraction algorithm is very similar to the low level unsigned addition algorithm. The principle difference is that the unsigned subtraction algorithm requires the result to be positive. That is when computing a-b the condition $|a| \geq |b|$ must be met for this algorithm to function properly. Keep in mind this low level algorithm is not meant to be used in higher level algorithms directly. This algorithm as will be shown can be used to create functional signed addition and subtraction algorithms.

For this algorithm a new variable is required to make the description simpler. Recall from section 1.3.1 that a mp_digit must be able to represent the range $0 \le x < 2\beta$ for the algorithms to work correctly. However, it is allowable that a mp_digit represent a larger range of values. For this algorithm we will assume that the variable γ represents the number of bits available in a mp_digit (this implies $2^{\gamma} > \beta$).

For example, the default for LibTomMath is to use a "unsigned long" for the mp_digit "type" while $\beta = 2^{28}$. In ISO C an "unsigned long" data type must be able to represent $0 \le x < 2^{32}$ meaning that in this case $\gamma = 32$.

```
Algorithm s_mp_sub.
Input. Two mp_ints a and b (|a| \ge |b|)
Output. The unsigned subtraction c = |a| - |b|.
1. min \leftarrow b.used
2. max \leftarrow a.used
3. If c.alloc < max then grow c to hold at least max digits. (mp\_qrow)
4. oldused \leftarrow c.used
5. c.used \leftarrow max
6. u \leftarrow 0
7. for n from 0 to min - 1 do
  7.1 \ c_n \leftarrow a_n - b_n - u
  7.2 \ u \leftarrow c_n >> (\gamma - 1)
  7.3 \ c_n \leftarrow c_n \pmod{\beta}
8. if min < max then do
  8.1 for n from min to max - 1 do
     8.1.1 c_n \leftarrow a_n - u
     8.1.2\ u \leftarrow c_n >> (\gamma - 1)
     8.1.3 c_n \leftarrow c_n \pmod{\beta}
9. if oldused > max then do
  9.1 for n from max to oldused - 1 do
     9.1.1 c_n \leftarrow 0
10. Clamp excess digits of c. (mp\_clamp).
11. Return(MP\_OKAY).
```

Figure 4.2: Algorithm s_mp_sub

Algorithm s_mp_sub. This algorithm performs the unsigned subtraction of two mp_int variables under the restriction that the result must be positive. That is when passing variables a and b the condition that $|a| \geq |b|$ must be met for the algorithm to function correctly. This algorithm is loosely based on algorithm 14.9 [2, pp. 595] and is similar to algorithm S in [1, pp. 267] as well. As was the case of the algorithm s_mp_add both other references lack discussion concerning various practical details such as when the inputs differ in magnitude.

The initial sorting of the inputs is trivial in this algorithm since a is guaranteed to have at least the same magnitude of b. Steps 1 and 2 set the min and max variables. Unlike the addition routine there is guaranteed to be no carry which means that the final result can be at most max digits in length as opposed to max + 1. Similar to the addition algorithm the **used** count of c is copied locally and set to the maximal count for the operation.

The subtraction loop that begins on step seven is essentially the same as the addition loop of algorithm s_mp_add except single precision subtraction is used instead. Note the use of the γ variable to extract the carry (also known as the borrow) within the subtraction loops. Under the assumption that two's complement single precision arithmetic is used this will successfully extract the desired carry.

For example, consider subtracting 0101_2 from 0100_2 where $\gamma=4$ and $\beta=2$. The least significant bit will force a carry upwards to the third bit which will be set to zero after the borrow. After the very first bit has been subtracted $4-1\equiv 0011_2$ will remain, When the third bit of 0101_2 is subtracted from the result it will cause another carry. In this case though the carry will be forced to propagate all the way to the most significant bit.

Recall that $\beta < 2^{\gamma}$. This means that if a carry does occur just before the $lg(\beta)$ 'th bit it will propagate all the way to the most significant bit. Thus, the high order bits of the mp_digit that are not part of the actual digit will either be all zero, or all one. All that is needed is a single zero or one bit for the carry. Therefore a single logical shift right by $\gamma - 1$ positions is sufficient to extract the carry. This method of carry extraction may seem awkward but the reason for it becomes apparent when the implementation is discussed.

If b has a smaller magnitude than a then step 9 will force the carry and copy operation to propagate through the larger input a into c. Step 10 will ensure that any leading digits of c above the max'th position are zeroed.

```
File: bn_s_mp_sub.c
016
      /* low level subtraction (assumes |a| > |b|), HAC pp.595 Algorithm 14.9 */
017
018
019
      s_mp_sub (mp_int * a, mp_int * b, mp_int * c)
020
021
        int
                olduse, res, min, max;
022
023
        /* find sizes */
024
        min = b->used;
025
        max = a->used;
026
027
        /* init result */
028
        if (c->alloc < max) {
          if ((res = mp_grow (c, max)) != MP_OKAY) {
029
030
            return res;
031
        }
032
```

```
033
        olduse = c->used;
034
        c->used = max;
035
036
037
          register mp_digit u, *tmpa, *tmpb, *tmpc;
038
          register int i;
039
040
          /* alias for digit pointers */
041
          tmpa = a->dp;
          tmpb = b->dp;
042
          tmpc = c->dp;
043
044
045
          /* set carry to zero */
          u = 0;
046
047
          for (i = 0; i < min; i++) {
048
            /* T[i] = A[i] - B[i] - U */
049
            *tmpc = *tmpa++ - *tmpb++ - u;
050
051
            /* U = carry bit of T[i]
052
             * Note this saves performing an AND operation since
             * if a carry does occur it will propagate all the way to the
053
054
             * MSB. As a result a single shift is enough to get the carry
055
             */
            u = *tmpc >> ((mp_digit)(CHAR_BIT * sizeof (mp_digit) - 1));
056
057
058
            /* Clear carry from T[i] */
059
            *tmpc++ &= MP_MASK;
060
061
062
          /* now copy higher words if any, e.g. if A has more digits than B */
063
          for (; i < max; i++) {
064
            /* T[i] = A[i] - U */
065
            *tmpc = *tmpa++ - u;
066
067
            /* U = carry bit of T[i] */
068
            u = *tmpc >> ((mp_digit)(CHAR_BIT * sizeof (mp_digit) - 1));
069
070
            /* Clear carry from T[i] */
071
            *tmpc++ &= MP_MASK;
072
073
074
          /* clear digits above used (since we may not have grown result above) */
```

Line 24 and 25 perform the initial hardcoded sorting of the inputs. In reality the min and max variables are only aliases and are only used to make the source code easier to read. Again the pointer alias optimization is used within this algorithm. Lines 41, 42 and 43 initialize the aliases for a, b and c respectively.

The first subtraction loop occurs on lines 46 through 60. The theory behind the subtraction loop is exactly the same as that for the addition loop. As remarked earlier there is an implementation reason for using the "awkward" method of extracting the carry (see line 56). The traditional method for extracting the carry would be to shift by $lg(\beta)$ positions and logically AND the least significant bit. The AND operation is required because all of the bits above the $lg(\beta)$ 'th bit will be set to one after a carry occurs from subtraction. This carry extraction requires two relatively cheap operations to extract the carry. The other method is to simply shift the most significant bit to the least significant bit thus extracting the carry with a single cheap operation. This optimization only works on twos compliment machines which is a safe assumption to make.

If a has a larger magnitude than b an additional loop (see lines 63 through 72) is required to propagate the carry through a and copy the result to c.

4.2.3 High Level Addition

Now that both lower level addition and subtraction algorithms have been established an effective high level signed addition algorithm can be established. This high level addition algorithm will be what other algorithms and developers will use to perform addition of mp_int data types.

Recall from section 5.2 that an mp_int represents an integer with an unsigned mantissa (the array of digits) and a sign flag. A high level addition is actually performed as a series of eight separate cases which can be optimized down to three unique cases.

```
Algorithm mp_add.

Input. Two mp_ints a and b

Output. The signed addition c = a + b.

1. if a.sign = b.sign then do

1.1 c.sign \leftarrow a.sign

1.2 c \leftarrow |a| + |b| (s.mp_add)

2. else do

2.1 if |a| < |b| then do (mp_cmp_mag)

2.1.1 c.sign \leftarrow b.sign

2.1.2 c \leftarrow |b| - |a| (s.mp_sub)

2.2 else do

2.2.1 c.sign \leftarrow a.sign

2.2.2 c \leftarrow |a| - |b|

3. Return(MP_cOKAY).
```

Figure 4.3: Algorithm mp_add

Algorithm mp_add. This algorithm performs the signed addition of two mp_int variables. There is no reference algorithm to draw upon from either [1] or [2] since they both only provide unsigned operations. The algorithm is fairly straightforward but restricted since subtraction can only produce positive results.

Figure 4.4 lists all of the eight possible input combinations and is sorted to show that only three specific cases need to be handled. The return code of the unsigned operations at step 1.2, 2.1.2 and 2.2.2 are forwarded to step three to check for errors. This simplifies the description of the algorithm considerably and best follows how the implementation actually was achieved.

Also note how the **sign** is set before the unsigned addition or subtraction is performed. Recall from the descriptions of algorithms s_mp_add and s_mp_sub that the mp_clamp function is used at the end to trim excess digits. The mp_clamp algorithm will set the **sign** to **MP_ZPOS** when the **used** digit count reaches zero.

For example, consider performing -a + a with algorithm mp_add. By the description of the algorithm the sign is set to $\mathbf{MP_NEG}$ which would produce a result of -0. However, since the sign is set first then the unsigned addition is performed the subsequent usage of algorithm mp_clamp within algorithm

Sign of a	Sign of b	a > b	Unsigned Operation	Result Sign Flag
+	+	Yes	c = a + b	a.sign
+	+	No	c = a + b	a.sign
_	_	Yes	c = a + b	a.sign
_	_	No	c = a + b	a.sign
+	_	No	c = b - a	b.sign
_	+	No	c = b - a	b.sign
+	_	Yes	c = a - b	a.sign
_	+	Yes	c = a - b	a.sign

Figure 4.4: Addition Guide Chart

 $s_{part} = 0$ to become 0.

```
File: bn_mp_add.c
016
017
      /* high level addition (handles signs) */
018
      int mp_add (mp_int * a, mp_int * b, mp_int * c)
019
020
                sa, sb, res;
        int
021
022
        /* get sign of both inputs */
023
        sa = a->sign;
024
        sb = b->sign;
025
026
        /* handle two cases, not four */
027
        if (sa == sb) {
028
          /* both positive or both negative */
029
          /* add their magnitudes, copy the sign */
030
          c->sign = sa;
          res = s_mp_add (a, b, c);
031
032
        } else {
          /* one positive, the other negative */
033
034
          /* subtract the one with the greater magnitude from */
035
          /* the one of the lesser magnitude. The result gets */
          /* the sign of the one with the greater magnitude. */
036
037
          if (mp_cmp_mag (a, b) == MP_LT) {
038
            c->sign = sb;
039
            res = s_mp_sub (b, a, c);
```

The source code follows the algorithm fairly closely. The most notable new source code addition is the usage of the *res* integer variable which is used to pass result of the unsigned operations forward. Unlike in the algorithm, the variable *res* is merely returned as is without explicitly checking it and returning the constant **MP_OKAY**. The observation is this algorithm will succeed or fail only if the lower level functions do so. Returning their return code is sufficient.

4.2.4 High Level Subtraction

The high level signed subtraction algorithm is essentially the same as the high level signed addition algorithm.

```
Algorithm mp_sub. Input. Two mp_ints a and b Output. The signed subtraction c = a - b.
```

```
1. if a.sign \neq b.sign then do 

1.1 c.sign \leftarrow a.sign 

1.2 c \leftarrow |a| + |b| (s\_mp\_add) 

2. else do 

2.1 if |a| \geq |b| then do (mp\_cmp\_mag) 

2.1.1 c.sign \leftarrow a.sign 

2.1.2 c \leftarrow |a| - |b| (s\_mp\_sub) 

2.2 else do 

2.2 else do 

2.2.1 c.sign \leftarrow \begin{cases} MP\_ZPOS & \text{if } a.sign = MP\_NEG \\ MP\_NEG & \text{otherwise} \end{cases} 

2.2.2 c \leftarrow |b| - |a| 

3. Return(MP\_OKAY).
```

Figure 4.5: Algorithm mp_sub

Algorithm mp_sub. This algorithm performs the signed subtraction of two inputs. Similar to algorithm mp_add there is no reference in either [1] or [2]. Also this algorithm is restricted by algorithm s_mp_sub. Chart 4.6 lists the eight possible inputs and the operations required.

Sign of a	Sign of b	$ a \ge b $	Unsigned Operation	Result Sign Flag
+	_	Yes	c = a + b	a.sign
+	_	No	c = a + b	a.sign
_	+	Yes	c = a + b	a.sign
_	+	No	c = a + b	a.sign
+	+	Yes	c = a - b	a.sign
_	_	Yes	c = a - b	a.sign
+	+	No	c = b - a	opposite of a.sign
_	_	No	c = b - a	opposite of a.sign

Figure 4.6: Subtraction Guide Chart

Similar to the case of algorithm mp_add the **sign** is set first before the unsigned addition or subtraction. That is to prevent the algorithm from producing -a - -a = -0 as a result.

```
File: bn_mp_sub.c
016
017
      /* high level subtraction (handles signs) */
018
019
      mp_sub (mp_int * a, mp_int * b, mp_int * c)
020
021
        int
                sa, sb, res;
022
023
        sa = a->sign;
024
        sb = b->sign;
025
026
        if (sa != sb) {
027
          /* subtract a negative from a positive, OR */
028
          /* subtract a positive from a negative. */
029
          /* In either case, ADD their magnitudes, */
          /* and use the sign of the first number. */
030
031
          c->sign = sa;
032
          res = s_mp_add (a, b, c);
033
        } else {
          /* subtract a positive from a positive, OR */
034
035
          /* subtract a negative from a negative. */
          /* First, take the difference between their */
036
          /* magnitudes, then... */
037
038
          if (mp_cmp_mag (a, b) != MP_LT) {
039
            /* Copy the sign from the first */
040
            c->sign = sa;
041
            /* The first has a larger or equal magnitude */
042
            res = s_mp_sub (a, b, c);
043
          } else {
044
            /* The result has the *opposite* sign from */
045
            /* the first number. */
046
            c->sign = (sa == MP_ZPOS) ? MP_NEG : MP_ZPOS;
047
            /* The second has a larger magnitude */
048
            res = s_mp_sub (b, a, c);
049
050
        }
051
        return res;
052
      }
```

053

Much like the implementation of algorithm mp_add the variable res is used to catch the return code of the unsigned addition or subtraction operations and forward it to the end of the function. On line 38 the "not equal to" MP_LT expression is used to emulate a "greater than or equal to" comparison.

4.3 Bit and Digit Shifting

It is quite common to think of a multiple precision integer as a polynomial in x, that is $y = f(\beta)$ where $f(x) = \sum_{i=0}^{n-1} a_i x^i$. This notation arises within discussion of Montgomery and Diminished Radix Reduction as well as Karatsuba multiplication and squaring.

In order to facilitate operations on polynomials in x as above a series of simple "digit" algorithms have to be established. That is to shift the digits left or right as well to shift individual bits of the digits left and right. It is important to note that not all "shift" operations are on radix- β digits.

4.3.1 Multiplication by Two

In a binary system where the radix is a power of two multiplication by two not only arises often in other algorithms it is a fairly efficient operation to perform. A single precision logical shift left is sufficient to multiply a single digit by two.

```
Algorithm mp_mul_2.
Input. One mp_int a
Output. b = 2a.
1. If b.alloc < a.used + 1 then grow b to hold a.used + 1 digits. (mp\_grow)
2. oldused \leftarrow b.used
3. b.used \leftarrow a.used
4. r \leftarrow 0
5. for n from 0 to a.used - 1 do
  5.1 \ rr \leftarrow a_n >> (lg(\beta) - 1)
  5.2 \ b_n \leftarrow (a_n << 1) + r \pmod{\beta}
  5.3 \ r \leftarrow rr
6. If r \neq 0 then do
  6.1 \ b_{n+1} \leftarrow r
  6.2 \ b.used \leftarrow b.used + 1
7. If b.used < oldused - 1 then do
  7.1 for n from b.used to oldused - 1 do
     7.1.1 \ b_n \leftarrow 0
8. b.sign \leftarrow a.sign
9. Return(MP\_OKAY).
```

Figure 4.7: Algorithm mp_mul_2

Algorithm mp_mul_2. This algorithm will quickly multiply a mp_int by two provided β is a power of two. Neither [1] nor [2] describe such an algorithm despite the fact it arises often in other algorithms. The algorithm is setup much like the lower level algorithm s_mp_add since it is for all intents and purposes equivalent to the operation b = |a| + |a|.

Step 1 and 2 grow the input as required to accommodate the maximum number of **used** digits in the result. The initial **used** count is set to *a.used* at step 4. Only if there is a final carry will the **used** count require adjustment.

Step 6 is an optimization implementation of the addition loop for this specific case. That is since the two values being added together are the same there is no need to perform two reads from the digits of a. Step 6.1 performs a single precision shift on the current digit a_n to obtain what will be the carry for the next iteration. Step 6.2 calculates the n'th digit of the result as single precision shift of a_n plus the previous carry. Recall from section 4.1 that $a_n << 1$ is equivalent to $a_n \cdot 2$. An iteration of the addition loop is finished with forwarding the carry to the next iteration.

Step 7 takes care of any final carry by setting the a.used'th digit of the

result to the carry and augmenting the **used** count of b. Step 8 clears any leading digits of b in case it originally had a larger magnitude than a.

```
File: bn_mp_mul_2.c
017
      /* b = a*2 */
018
      int mp_mul_2(mp_int * a, mp_int * b)
019
020
        int
                x, res, oldused;
021
022
        /* grow to accomodate result */
023
        if (b->alloc < a->used + 1) {
024
          if ((res = mp_grow (b, a->used + 1)) != MP_OKAY) {
025
            return res;
026
        }
027
028
029
        oldused = b->used;
030
        b->used = a->used;
031
032
033
          register mp_digit r, rr, *tmpa, *tmpb;
034
035
          /* alias for source */
036
          tmpa = a->dp;
037
038
          /* alias for dest */
039
          tmpb = b->dp;
040
041
          /* carry */
042
          r = 0;
043
          for (x = 0; x < a->used; x++) {
044
045
            /* get what will be the *next* carry bit from the
046
             * MSB of the current digit
047
             */
            rr = *tmpa >> ((mp_digit)(DIGIT_BIT - 1));
048
049
050
            /* now shift up this digit, add in the carry [from the previous] */
051
            *tmpb++ = ((*tmpa++ << ((mp_digit)1)) | r) & MP_MASK;
052
            /* copy the carry that would be from the source
053
054
             * digit into the next iteration
```

```
*/
055
056
            r = rr;
057
058
059
          /* new leading digit? */
          if (r != 0) {
060
061
            /* add a MSB which is always 1 at this point */
062
            *tmpb = 1;
            ++(b->used);
063
          }
064
065
066
          /* now zero any excess digits on the destination
           * that we didn't write to
067
068
069
          tmpb = b->dp + b->used;
070
          for (x = b-)used; x < oldused; x++) {
071
            *tmpb++ = 0;
072
073
074
        b->sign = a->sign;
075
        return MP_OKAY;
076
      }
```

This implementation is essentially an optimized implementation of s_mp_add for the case of doubling an input. The only noteworthy difference is the use of the logical shift operator on line 51 to perform a single precision doubling.

4.3.2 Division by Two

A division by two can just as easily be accomplished with a logical shift right as multiplication by two can be with a logical shift left.

```
Algorithm mp_div_2.
Input. One mp_int a
Output. b = a/2.
1. If b.alloc < a.used then grow b to hold a.used digits. (mp\_grow)
2. If the reallocation failed return (MP\_MEM).
3. oldused \leftarrow b.used
4.\ b.used \leftarrow a.used
5. r \leftarrow 0
6. for n from b.used - 1 to 0 do
  6.1 \ rr \leftarrow a_n \pmod{2}
  6.2 \ b_n \leftarrow (a_n >> 1) + (r << (lg(\beta) - 1)) \pmod{\beta}
  6.3 \ r \leftarrow rr
7. If b.used < oldused - 1 then do
  7.1 for n from b.used to oldused - 1 do
    7.1.1 \ b_n \leftarrow 0
8. b.sign \leftarrow a.sign
9. Clamp excess digits of b. (mp\_clamp)
10. Return(MP\_OKAY).
```

Figure 4.8: Algorithm mp_div_2

Algorithm mp_div_2. This algorithm will divide an mp_int by two using logical shifts to the right. Like mp_mul_2 it uses a modified low level addition core as the basis of the algorithm. Unlike mp_mul_2 the shift operations work from the leading digit to the trailing digit. The algorithm could be written to work from the trailing digit to the leading digit however, it would have to stop one short of a.used-1 digits to prevent reading past the end of the array of digits.

Essentially the loop at step 6 is similar to that of mp_mul_2 except the logical shifts go in the opposite direction and the carry is at the least significant bit not the most significant bit.

```
File: bn_mp_div_2.c
016
017     /* b = a/2 */
018     int mp_div_2(mp_int * a, mp_int * b)
019     {
020         int        x, res, oldused;
021
022     /* copy */
```

```
023
        if (b->alloc < a->used) {
024
          if ((res = mp_grow (b, a->used)) != MP_OKAY) {
025
            return res;
026
        }
027
028
029
        oldused = b->used;
030
        b->used = a->used;
031
032
          register mp_digit r, rr, *tmpa, *tmpb;
033
034
          /* source alias */
035
          tmpa = a->dp + b->used - 1;
036
037
          /* dest alias */
038
          tmpb = b->dp + b->used - 1;
039
040
          /* carry */
041
          r = 0;
042
          for (x = b-)used - 1; x >= 0; x--) {
043
            /* get the carry for the next iteration */
044
            rr = *tmpa & 1;
045
046
            /* shift the current digit, add in carry and store */
            *tmpb-- = (*tmpa-- >> 1) | (r << (DIGIT_BIT - 1));
047
048
049
            /* forward carry to next iteration */
050
            r = rr;
051
          }
052
053
          /* zero excess digits */
054
          tmpb = b->dp + b->used;
055
          for (x = b-)used; x < oldused; x++) {
            *tmpb++ = 0;
056
057
058
059
        b->sign = a->sign;
060
        mp_clamp (b);
        return MP_OKAY;
061
062
      }
```

4.4 Polynomial Basis Operations

Recall from section 4.3 that any integer can be represented as a polynomial in x as $y = f(\beta)$. Such a representation is also known as the polynomial basis [3, pp. 48]. Given such a notation a multiplication or division by x amounts to shifting whole digits a single place. The need for such operations arises in several other higher level algorithms such as Barrett and Montgomery reduction, integer division and Karatsuba multiplication.

Converting from an array of digits to polynomial basis is very simple. Consider the integer $y \equiv (a_2, a_1, a_0)_{\beta}$ and recall that $y = \sum_{i=0}^{2} a_i \beta^i$. Simply replace β with x and the expression is in polynomial basis. For example, f(x) = 8x + 9 is the polynomial basis representation for 89 using radix ten. That is, f(10) = 8(10) + 9 = 89.

4.4.1 Multiplication by x

Given a polynomial in x such as $f(x) = a_n x^n + a_{n-1} x^{n-1} + ... + a_0$ multiplying by x amounts to shifting the coefficients up one degree. In this case $f(x) \cdot x = a_n x^{n+1} + a_{n-1} x^n + ... + a_0 x$. From a scalar basis point of view multiplying by x is equivalent to multiplying by the integer β .

```
Algorithm mp_lshd.
Input. One mp_int a and an integer b
Output. a \leftarrow a \cdot \beta^b (equivalent to multiplication by x^b).
1. If b \leq 0 then return(MP\_OKAY).
2. If a.alloc < a.used + b then grow a to at least a.used + b digits. (mp\_grow).
3. If the reallocation failed return (MP\_MEM).
4. \ a.used \leftarrow a.used + b
5. i \leftarrow a.used - 1
6. j \leftarrow a.used - 1 - b
7. for n from a.used - 1 to b do
  7.1 \ a_i \leftarrow a_j
  7.2 \ i \leftarrow i-1
  7.3 j \leftarrow j - 1
8. for n from 0 to b-1 do
  8.1 \ a_n \leftarrow 0
9. Return(MP_{-}OKAY).
```

Figure 4.9: Algorithm mp_lshd

Algorithm mp_lshd. This algorithm multiplies an mp_int by the b'th power of x. This is equivalent to multiplying by β^b . The algorithm differs from the other algorithms presented so far as it performs the operation in place instead storing the result in a separate location. The motivation behind this change is due to the way this function is typically used. Algorithms such as mp_add store the result in an optionally different third mp_int because the original inputs are often still required. Algorithm mp_lshd (and similarly algorithm mp_rshd) is typically used on values where the original value is no longer required. The algorithm will return success immediately if $b \leq 0$ since the rest of algorithm is only valid when b > 0.

First the destination a is grown as required to accommodate the result. The counters i and j are used to form a sliding window over the digits of a of length b. The head of the sliding window is at i (the leading digit) and the tail at j (the trailing digit). The loop on step 7 copies the digit from the tail to the head. In each iteration the window is moved down one digit. The last loop on step 8 sets the lower b digits to zero.




Figure 4.10: Sliding Window Movement

```
File: bn_mp_lshd.c
016
017
      /* shift left a certain amount of digits */
018
      int mp_lshd (mp_int * a, int b)
019
020
        int
                x, res;
021
022
        /* if its less than zero return */
        if (b <= 0) {
023
024
          return MP_OKAY;
025
026
027
        /* grow to fit the new digits */
028
        if (a->alloc < a->used + b) \{
           if ((res = mp_grow (a, a->used + b)) != MP_OKAY) \{
029
030
             return res;
031
           }
        }
032
033
034
          register mp_digit *top, *bottom;
035
036
037
          /* increment the used by the shift amount then copy upwards */
038
          a->used += b;
```

```
039
040
           /* top */
           top = a \rightarrow dp + a \rightarrow used - 1;
041
042
043
           /* base */
044
           bottom = a \rightarrow dp + a \rightarrow used - 1 - b;
045
046
           /* much like mp_rshd this is implemented using a sliding window
047
            * except the window goes the otherway around. Copying from
048
            * the bottom to the top. see bn_mp_rshd.c for more info.
049
050
           for (x = a-)used - 1; x >= b; x--) {
051
             *top-- = *bottom--;
052
053
054
           /* zero the lower digits */
055
           top = a->dp;
           for (x = 0; x < b; x++) {
056
057
             *top++ = 0;
058
059
060
        return MP_OKAY;
061
```

The if statement on line 23 ensures that the b variable is greater than zero. The **used** count is incremented by b before the copy loop begins. This elminates the need for an additional variable in the for loop. The variable top on line 41 is an alias for the leading digit while bottom on line 44 is an alias for the trailing edge. The aliases form a window of exactly b digits over the input.

4.4.2 Division by x

Division by powers of x is easily achieved by shifting the digits right and removing any that will end up to the right of the zero'th digit.

```
Algorithm mp_rshd.
Input. One mp_int a and an integer b
Output. a \leftarrow a/\beta^b (Divide by x^b).
1. If b \leq 0 then return.
2. If a.used \leq b then do
  2.1 Zero a. (mp\_zero).
  2.2 Return.
3. i \leftarrow 0
4. j \leftarrow b
5. for n from 0 to a.used - b - 1 do
  5.1 \ a_i \leftarrow a_j
  5.2 i \leftarrow i + 1
  5.3 j \leftarrow j + 1
6. for n from a.used - b to a.used - 1 do
  6.1 \ a_n \leftarrow 0
7. a.used \leftarrow a.used - b
8. Return.
```

Figure 4.11: Algorithm mp_rshd

Algorithm mp_rshd. This algorithm divides the input in place by the b'th power of x. It is analogous to dividing by a β^b but much quicker since it does not require single precision division. This algorithm does not actually return an error code as it cannot fail.

If the input b is less than one the algorithm quickly returns without performing any work. If the **used** count is less than or equal to the shift count b then it will simply zero the input and return.

After the trivial cases of inputs have been handled the sliding window is setup. Much like the case of algorithm mp_lshd a sliding window that is b digits wide is used to copy the digits. Unlike mp_lshd the window slides in the opposite direction from the trailing to the leading digit. Also the digits are copied from the leading to the trailing edge.

Once the window copy is complete the upper digits must be zeroed and the **used** count decremented.

```
File: bn_mp_rshd.c
016
017  /* shift right a certain amount of digits */
018  void mp_rshd (mp_int * a, int b)
```

```
019
020
        int
                x;
021
022
        /* if b <= 0 then ignore it */
023
        if (b <= 0) {
024
          return;
025
026
027
        /* if b > used then simply zero it and return */
        if (a->used <= b) {
028
029
          mp_zero (a);
030
         return;
031
032
033
034
          register mp_digit *bottom, *top;
035
036
          /* shift the digits down */
037
038
          /* bottom */
039
          bottom = a->dp;
040
          /* top [offset into digits] */
041
042
          top = a->dp + b;
043
044
          /* this is implemented as a sliding window where
045
           * the window is b-digits long and digits from
046
           * the top of the window are copied to the bottom
047
048
           * e.g.
049
050
           b-2 | b-1 | b0 | b1 | b2 | ... | bb |
051
                        \----/
                                                   --->
052
           */
053
054
          for (x = 0; x < (a-)used - b); x++) {
055
            *bottom++ = *top++;
056
057
058
          /* zero the top digits */
059
          for (; x < a > used; x++) {
060
            *bottom++ = 0;
```

The only noteworthy element of this routine is the lack of a return type.

- Will update later to give it a return type...Tom

4.5 Powers of Two

Now that algorithms for moving single bits as well as whole digits exist algorithms for moving the "in between" distances are required. For example, to quickly multiply by 2^k for any k without using a full multiplier algorithm would prove useful. Instead of performing single shifts k times to achieve a multiplication by $2^{\pm k}$ a mixture of whole digit shifting and partial digit shifting is employed.

4.5.1 Multiplication by Power of Two

```
Algorithm mp_mul_2d.
Input. One mp_int a and an integer b
Output. c \leftarrow a \cdot 2^b.
1. c \leftarrow a. (mp\_copy)
2. If c.alloc < c.used + |b/lg(\beta)| + 2 then grow c accordingly.
3. If the reallocation failed return (MP\_MEM).
4. If b \geq lg(\beta) then
  4.1 \ c \leftarrow c \cdot \beta^{\lfloor b/lg(\beta) \rfloor} \ (mp\_lshd).
  4.2 If step 4.1 failed return(MP\_MEM).
5. d \leftarrow b \pmod{\lg(\beta)}
6. If d \neq 0 then do
  6.1 \ mask \leftarrow 2^d
  6.2 \ r \leftarrow 0
  6.3 for n from 0 to c.used - 1 do
      6.3.1 \ rr \leftarrow c_n >> (lg(\beta) - d) \ (\text{mod } mask)
     6.3.2 \ c_n \leftarrow (c_n << d) + r \pmod{\beta}
     6.3.3 \ r \leftarrow rr
  6.4 \text{ If } r > 0 \text{ then do}
      6.4.1 \ c_{c.used} \leftarrow r
      6.4.2 \ c.used \leftarrow c.used + 1
7. Return(MP\_OKAY).
```

Figure 4.12: Algorithm mp_mul_2d

Algorithm mp_mul_2d. This algorithm multiplies a by 2^b and stores the result in c. The algorithm uses algorithm mp_lshd and a derivative of algorithm mp_mul_2 to quickly compute the product.

First the algorithm will multiply a by $x^{\lfloor b/lg(\beta)\rfloor}$ which will ensure that the remainder multiplicand is less than β . For example, if b=37 and $\beta=2^{28}$ then this step will multiply by x leaving a multiplication by $2^{37-28}=2^9$ left.

After the digits have been shifted appropriately at most $lg(\beta)-1$ shifts are left to perform. Step 5 calculates the number of remaining shifts required. If it is non-zero a modified shift loop is used to calculate the remaining product. Essentially the loop is a generic version of algorith mp_mul2 designed to handle any shift count in the range $1 \le x < lg(\beta)$. The mask variable is used to extract the upper d bits to form the carry for the next iteration.

This algorithm is loosely measured as a O(2n) algorithm which means that if the input is *n*-digits that it takes 2n "time" to complete. It is possible to optimize this algorithm down to a O(n) algorithm at a cost of making the

algorithm slightly harder to follow.

```
File: bn_mp_mul_2d.c
017
      /* shift left by a certain bit count */
018
      int mp_mul_2d (mp_int * a, int b, mp_int * c)
019
020
        mp_digit d;
021
        int
                res;
022
023
        /* copy */
        if (a != c) {
024
025
           if ((res = mp_copy (a, c)) != MP_OKAY) {
026
             return res;
027
028
        }
029
        if (c->alloc < (int)(c->used + b/DIGIT_BIT + 1)) {
030
031
           if ((res = mp_grow (c, c->used + b / DIGIT_BIT + 1)) != MP_OKAY) {
032
             return res;
033
034
        }
035
036
        /* shift by as many digits in the bit count */
        if (b >= (int)DIGIT_BIT) {
037
038
          if ((res = mp_lshd (c, b / DIGIT_BIT)) != MP_OKAY) {
039
            return res;
040
041
042
043
        /* shift any bit count < DIGIT_BIT */
044
        d = (mp_digit) (b % DIGIT_BIT);
045
        if (d != 0) {
046
          register mp_digit *tmpc, shift, mask, r, rr;
047
          register int x;
048
          /* bitmask for carries */
049
050
          mask = (((mp_digit)1) << d) - 1;</pre>
051
          /* shift for msbs */
052
053
          shift = DIGIT_BIT - d;
054
055
          /* alias */
```

```
056
          tmpc = c->dp;
057
058
          /* carry */
059
               = 0;
          for (x = 0; x < c->used; x++) {
060
            /* get the higher bits of the current word */
061
062
            rr = (*tmpc >> shift) & mask;
063
064
            /* shift the current word and OR in the carry */
065
            *tmpc = ((*tmpc << d) | r) & MP_MASK;
066
            ++tmpc;
067
068
            /* set the carry to the carry bits of the current word */
069
070
          }
071
072
          /* set final carry */
          if (r != 0) {
073
              c \rightarrow dp[(c \rightarrow used) ++] = r;
074
075
076
077
        mp_clamp (c);
078
        return MP_OKAY;
079
```

Notes to be revised when code is updated. – Tom

4.5.2 Division by Power of Two

```
Algorithm mp_div_2d.
Input. One mp_int a and an integer b
Output. c \leftarrow \lfloor a/2^b \rfloor, d \leftarrow a \pmod{2^b}.
1. If b \leq 0 then do
   1.1 \ c \leftarrow a \ (mp\_copy)
   1.2 \ d \leftarrow 0 \ (mp\_zero)
   1.3 Return(MP\_OKAY).
2. \ c \leftarrow a
3. d \leftarrow a \pmod{2^b} \pmod{2d}
4. If b \ge lg(\beta) then do
  4.1 \ c \leftarrow \lfloor c/\beta^{\lfloor b/lg(\beta)\rfloor} \rfloor \ (mp\_rshd).
5. k \leftarrow b \pmod{\lg(\beta)}
6. If k \neq 0 then do
   6.1 \ mask \leftarrow 2^k
   6.2 \ r \leftarrow 0
   6.3 \text{ for } n \text{ from } c.used - 1 \text{ to } 0 \text{ do}
      6.3.1 \ rr \leftarrow c_n \ (\text{mod } mask)
      6.3.2 c_n \leftarrow (c_n >> k) + (r << (lg(\beta) - k))
      6.3.3 \ r \leftarrow rr
7. Clamp excess digits of c. (mp\_clamp)
8. Return(MP\_OKAY).
```

Figure 4.13: Algorithm mp_div_2d

Algorithm mp_div_2d. This algorithm will divide an input a by 2^b and produce the quotient and remainder. The algorithm is designed much like algorithm mp_mul_2d by first using whole digit shifts then single precision shifts. This algorithm will also produce the remainder of the division by using algorithm mp_mod_2d.

```
File: bn_mp_div_2d.c
016
017
      /* shift right by a certain bit count (store quotient in c, optional remaind
      er in d) */
018
      int mp_div_2d (mp_int * a, int b, mp_int * c, mp_int * d)
019
020
        mp_digit D, r, rr;
021
        int
                x, res;
022
        mp_int t;
023
```

```
024
025
        /* if the shift count is <= 0 then we do no work */</pre>
026
        if (b <= 0) {
027
          res = mp_copy (a, c);
          if (d != NULL) \{
028
029
            mp_zero (d);
030
          }
031
          return res;
032
033
        if ((res = mp_init (&t)) != MP_OKAY) {
034
035
          return res;
036
037
038
        /* get the remainder */
039
        if (d != NULL) {
040
          if ((res = mp_mod_2d (a, b, &t)) != MP_OKAY) {
041
            mp_clear (&t);
042
            return res;
          }
043
044
        }
045
046
        /* copy */
047
        if ((res = mp_copy (a, c)) != MP_OKAY) {
048
          mp_clear (&t);
049
          return res;
050
        }
051
052
        /* shift by as many digits in the bit count */
053
        if (b >= (int)DIGIT_BIT) {
054
          mp_rshd (c, b / DIGIT_BIT);
055
056
        /* shift any bit count < DIGIT_BIT */
057
        D = (mp_digit) (b % DIGIT_BIT);
058
        if (D != 0) {
059
060
          register mp_digit *tmpc, mask, shift;
061
062
          /* mask */
063
          mask = (((mp_digit)1) << D) - 1;</pre>
064
          /* shift for lsb */
065
```

```
066
          shift = DIGIT_BIT - D;
067
068
          /* alias */
069
          tmpc = c \rightarrow dp + (c \rightarrow used - 1);
070
071
          /* carry */
072
          r = 0:
073
          for (x = c-)used - 1; x >= 0; x--) {
074
             /* get the lower bits of this word in a temp */
075
             rr = *tmpc & mask;
076
077
             /* shift the current word and mix in the carry bits from the previous
      word */
             *tmpc = (*tmpc >> D) | (r << shift);
078
079
             --tmpc;
080
081
             /* set the carry to the carry bits of the current word found above */
082
             r = rr;
083
        }
084
085
        mp_clamp (c);
086
        if (d != NULL) {
087
          mp_exch (&t, d);
088
089
        mp_clear (&t);
090
        return MP_OKAY;
091
```

The implementation of algorithm mp_div_2d is slightly different than the algorithm specifies. The remainder d may be optionally ignored by passing **NULL** as the pointer to the mp_int variable. The temporary mp_int variable t is used to hold the result of the remainder operation until the end. This allows d and a to represent the same mp_int without modifying a before the quotient is obtained.

The remainder of the source code is essentially the same as the source code for mp_mul_2d. (- Fix this paragraph up later, Tom).

4.5.3 Remainder of Division by Power of Two

The last algorithm in the series of polynomial basis power of two algorithms is calculating the remainder of division by 2^b . This algorithm benefits from

the fact that in two complement arithmetic $a \pmod{2^b}$ is the same as $a \pmod{2^b-1}$.

```
Algorithm mp_mod_2d.
Input. One mp_int a and an integer b
Output. c \leftarrow a \pmod{2^b}.
1. If b \leq 0 then do
  1.1 \ c \leftarrow 0 \ (mp\_zero)
  1.2 Return(MP\_OKAY).
2. If b > a.used \cdot lg(\beta) then do
  2.1 \ c \leftarrow a \ (mp\_copy)
  2.2 Return the result of step 2.1.
3. \ c \leftarrow a
4. If step 3 failed return(MP_MEM).
5. for n from \lceil b/lg(\beta) \rceil to c.used do
  5.1 c_n \leftarrow 0
6. k \leftarrow b \pmod{lq(\beta)}
7. c_{\lfloor b/lg(\beta) \rfloor} \leftarrow c_{\lfloor b/lg(\beta) \rceil} \pmod{2^k}.
8. Clamp excess digits of c. (mp\_clamp)
9. Return(MP\_OKAY).
```

Figure 4.14: Algorithm mp_mod_2d

Algorithm mp_mod_2d. This algorithm will quickly calculate the value of $a \pmod{2^b}$. First if b is less than or equal to zero the result is set to zero. If b is greater than the number of bits in a then it simply copies a to c and returns. Otherwise, a is copied to b, leading digits are removed and the remaining leading digit is trimed to the exact bit count.

```
File: bn_mp_mod_2d.c
016
017
      /* calc a value mod 2**b */
018
019
      mp_mod_2d (mp_int * a, int b, mp_int * c)
020
      {
021
        int
                 x, res;
022
023
        /* if b is <= 0 then zero the int */</pre>
        if (b <= 0) {
024
025
          mp_zero (c);
```

```
026
          return MP_OKAY;
027
028
029
        /* if the modulus is larger than the value than return */
030
        if (b > (int) (a->used * DIGIT_BIT)) {
031
          res = mp_copy (a, c);
032
          return res;
033
        }
034
035
        /* copy */
036
        if ((res = mp_copy (a, c)) != MP_OKAY) {
037
          return res;
038
        }
039
040
        /* zero digits above the last digit of the modulus */
041
        for (x = (b / DIGIT_BIT) + ((b % DIGIT_BIT) == 0 ? 0 : 1); x < c->used; x+
      +) {
042
          c->dp[x] = 0;
043
044
        /* clear the digit that is not completely outside/inside the modulus */
045
        c->dp[b / DIGIT_BIT] &=
          (mp_digit) ((((mp_digit) 1) << (((mp_digit) b) % DIGIT_BIT)) - ((mp_digit)</pre>
046
      t) 1));
047
        mp_clamp (c);
048
        return MP_OKAY;
049
```

⁻ Add comments later, Tom.

Exercises

- [3] Devise an algorithm that performs $a \cdot 2^b$ for generic values of b in O(n) time.
- [3] Devise an efficient algorithm to multiply by small low hamming weight values such as 3, 5 and 9. Extend it to handle all values upto 64 with a hamming weight less than three.
- [2] Modify the preceding algorithm to handle values of the form $2^k 1$ as well.
- [3] Using only algorithms mp_mul_2, mp_div_2 and mp_add create an algorithm to multiply two integers in roughly $O(2n^2)$ time for any n-bit input. Note that the time of addition is ignored in the calculation.
- [5] Improve the previous algorithm to have a working time of at most $O\left(2^{(k-1)}n + \left(\frac{2n^2}{k}\right)\right)$ for an appropriate choice of k. Again ignore the cost of addition.
- [2] Devise a chart to find optimal values of k for the previous problem for $n = 64 \dots 1024$ in steps of 64.
- [2] Using only algorithms mp_abs and mp_sub devise another method for calculating the result of a signed comparison.

Chapter 5

Multiplication and Squaring

5.1 The Multipliers

For most number theoretic problems including certain public key cryptographic algorithms, the "multipliers" form the most important subset of algorithms of any multiple precision integer package. The set of multiplier algorithms include integer multiplication, squaring and modular reduction where in each of the algorithms single precision multiplication is the dominant operation performed. This chapter will discuss integer multiplication and squaring, leaving modular reductions for the subsequent chapter.

The importance of the multiplier algorithms is for the most part driven by the fact that certain popular public key algorithms are based on modular exponentiation, that is computing $d \equiv a^b \pmod{c}$ for some arbitrary choice of a, b, c and d. During a modular exponentiation the majority¹ of the processor time is spent performing single precision multiplications.

For centuries general purpose multiplication has required a lengthly $O(n^2)$ process, whereby each digit of one multiplicand has to be multiplied against every digit of the other multiplicand. Traditional long-hand multiplication is based on this process; while the techniques can differ the overall algorithm used is essentially the same. Only "recently" have faster algorithms been studied. First Karatsuba multiplication was discovered in 1962. This algorithm can

 $^{^1\}mathrm{Roughly}$ speaking a modular exponentiation will spend about 40% of the time performing modular reductions, 35% of the time performing squaring and 25% of the time performing multiplications.

multiply two numbers with considerably fewer single precision multiplications when compared to the long-hand approach. This technique led to the discovery of polynomial basis algorithms (*good reference?*) and subquently Fourier Transform based solutions.

5.2 Multiplication

5.2.1 The Baseline Multiplication

Computing the product of two integers in software can be achieved using a trivial adaptation of the standard $O(n^2)$ long-hand multiplication algorithm that school children are taught. The algorithm is considered an $O(n^2)$ algorithm since for two n-digit inputs n^2 single precision multiplications are required. More specifically for a m and n digit input $m \cdot n$ single precision multiplications are required. To simplify most discussions, it will be assumed that the inputs have comparable number of digits.

The "baseline multiplication" algorithm is designed to act as the "catch-all" algorithm, only to be used when the faster algorithms cannot be used. This algorithm does not use any particularly interesting optimizations and should ideally be avoided if possible. One important facet of this algorithm, is that it has been modified to only produce a certain amount of output digits as resolution. The importance of this modification will become evident during the discussion of Barrett modular reduction. Recall that for a n and m digit input the product will be at most n+m digits. Therefore, this algorithm can be reduced to a full multiplier by having it produce n+m digits of the product.

Recall from sub-section 4.2.2 the definition of γ as the number of bits in the type $\mathbf{mp_digit}$. We shall now extend the variable set to include α which shall represent the number of bits in the type $\mathbf{mp_word}$. This implies that $2^{\alpha} > 2 \cdot \beta^2$. The constant $\delta = 2^{\alpha - 2lg(\beta)}$ will represent the maximal weight of any column in a product (see sub-section 5.2.2 for more information).

89

```
Algorithm s_mp_mul_digs.
Input. mp_int a, mp_int b and an integer digs
Output. c \leftarrow |a| \cdot |b| \pmod{\beta^{digs}}.
1. If min(a.used, b.used) < \delta then do
  1.1 Calculate c = |a| \cdot |b| by the Comba method (see algorithm 5.5).
  1.2 Return the result of step 1.1
Allocate and initialize a temporary mp_int.
2. Init t to be of size digs
3. If step 2 failed return (MP\_MEM).
4. t.used \leftarrow digs
Compute the product.
5. for ix from 0 to a.used - 1 do
  5.1\ u \leftarrow 0
  5.2 \ pb \leftarrow \min(b.used, digs - ix)
  5.3 If pb < 1 then goto step 6.
  5.4 for iy from 0 to pb-1 do
     5.4.1 \ \hat{r} \leftarrow t_{iy+ix} + a_{ix} \cdot b_{iy} + u
     5.4.2 \ t_{iy+ix} \leftarrow \hat{r} \ (\text{mod } \beta)
     5.4.3 \ u \leftarrow |\hat{r}/\beta|
  5.5 if ix + pb < digs then do
     5.5.1 \ t_{ix+pb} \leftarrow u
6. Clamp excess digits of t.
7. Swap c with t
8. Clear t
9. Return(MP\_OKAY).
```

Figure 5.1: Algorithm s_mp_mul_digs

Algorithm s_mp_mul_digs. This algorithm computes the unsigned product of two inputs a and b, limited to an output precision of digs digits. While it may seem a bit awkward to modify the function from its simple $O(n^2)$ description, the usefulness of partial multipliers will arise in a subsequent algorithm. The algorithm is loosely based on algorithm 14.12 from [2, pp. 595] and is similar to Algorithm M of Knuth [1, pp. 268]. Algorithm s_mp_mul_digs differs from these cited references since it can produce a variable output precision regardless of the precision of the inputs.

The first thing this algorithm checks for is whether a Comba multiplier can

be used instead. If the minimum digit count of either input is less than δ , then the Comba method may be used instead. After the Comba method is ruled out, the baseline algorithm begins. A temporary mp_int variable t is used to hold the intermediate result of the product. This allows the algorithm to be used to compute products when either a=c or b=c without overwriting the inputs.

All of step 5 is the infamous $O(n^2)$ multiplication loop slightly modified to only produce upto digs digits of output. The pb variable is given the count of digits to read from b inside the nested loop. If $pb \leq 1$ then no more output digits can be produced and the algorithm will exit the loop. The best way to think of the loops are as a series of $pb \times 1$ multiplications. That is, in each pass of the innermost loop a_{ix} is multiplied against b and the result is added (with an appropriate shift) to t.

For example, consider multiplying 576 by 241. That is equivalent to computing $10^{0}(1)(576) + 10^{1}(4)(576) + 10^{2}(2)(576)$ which is best visualized in the following table.

			5	7	6	
×			2	4	1	
1	2 3	3 8	5 6 8	7 1 1	6 6 6	

Figure 5.2: Long-Hand Multiplication Diagram

Each row of the product is added to the result after being shifted to the left (multiplied by a power of the radix) by the appropriate count. That is in pass ix of the inner loop the product is added starting at the ix'th digit of the reult.

Step 5.4.1 introduces the hat symbol $(e.g.\ \hat{r})$ which represents a double precision variable. The multiplication on that step is assumed to be a double wide output single precision multiplication. That is, two single precision variables are multiplied to produce a double precision result. The step is somewhat optimized from a long-hand multiplication algorithm because the carry from the addition in step 5.4.1 is propagated through the nested loop. If the carry was not propagated immediately it would overflow the single precision digit t_{ix+iy} and the result would be lost.

At step 5.5 the nested loop is finished and any carry that was left over should be forwarded. The carry does not have to be added to the ix + pb'th digit since

that digit is assumed to be zero at this point. However, if $ix + pb \ge digs$ the carry is not set as it would make the result exceed the precision requested.

```
File: bn_s_mp_mul_digs.c
017
      /* multiplies |a|*|b| and only computes upto digs digits of result
018
       * HAC pp. 595, Algorithm 14.12 Modified so you can control how
019
       * many digits of output are created.
020
       */
021
      int
022
      s_mp_mul_digs (mp_int * a, mp_int * b, mp_int * c, int digs)
023
024
        mp_int t;
025
        int
                res, pa, pb, ix, iy;
026
        mp_digit u;
027
        mp_word r;
028
        mp_digit tmpx, *tmpt, *tmpy;
029
030
        /* can we use the fast multiplier? */
031
        if (((digs) < MP_WARRAY) &&
032
            MIN (a->used, b->used) <
033
                (1 << ((CHAR_BIT * sizeof (mp_word)) - (2 * DIGIT_BIT)))) {
034
          return fast_s_mp_mul_digs (a, b, c, digs);
035
036
037
        if ((res = mp_init_size (&t, digs)) != MP_OKAY) {
038
          return res;
039
040
        t.used = digs;
041
042
        /* compute the digits of the product directly */
043
        pa = a->used;
044
        for (ix = 0; ix < pa; ix++) \{
045
          /* set the carry to zero */
046
          u = 0;
047
048
          /* limit ourselves to making digs digits of output */
049
          pb = MIN (b->used, digs - ix);
050
051
          /* setup some aliases */
052
          /* copy of the digit from a used within the nested loop */
053
          tmpx = a->dp[ix];
054
```

```
055
          /* an alias for the destination shifted ix places */
056
          tmpt = t.dp + ix;
057
058
          /* an alias for the digits of b */
059
          tmpy = b->dp;
060
061
          /* compute the columns of the output and propagate the carry */
062
          for (iy = 0; iy < pb; iy++) \{
            /* compute the column as a mp_word */
063
064
                    = ((mp\_word)*tmpt) +
                       ((mp\_word)tmpx) * ((mp\_word)*tmpy++) +
065
066
                       ((mp_word) u);
067
068
            /* the new column is the lower part of the result */
069
            *tmpt++ = (mp_digit) (r & ((mp_word) MP_MASK));
070
071
            /* get the carry word from the result */
072
                    = (mp_digit) (r >> ((mp_word) DIGIT_BIT));
073
          }
074
          /* set carry if it is placed below digs */
075
          if (ix + iy < digs) \{
076
            *tmpt = u;
077
        }
078
079
080
        mp_clamp (&t);
081
        mp_exch (&t, c);
082
083
        mp_clear (&t);
        return MP_OKAY;
084
085
      }
```

Lines 31 to 35 determine if the Comba method can be used first. The conditions for using the Comba routine are that $\min(a.used, b.used) < \delta$ and the number of digits of output is less than **MP_WARRAY**. This new constant is used to control the stack usage in the Comba routines. By default it is set to δ but can be reduced when memory is at a premium.

Of particular importance is the calculation of the ix + iy'th column on lines 64, 65 and 66. Note how all of the variables are cast to the type $\mathbf{mp_word}$, which is also the type of variable \hat{r} . That is to ensure that double precision operations are used instead of single precision. The multiplication on line 65 makes use of a specific GCC optimizer behaviour. On the outset it looks like the

compiler will have to use a double precision multiplication to produce the result required. Such an operation would be horribly slow on most processors and drag this to a crawl. However, GCC is smart enough to realize that double wide output single precision multipliers can be used. For example, the instruction "MUL" on the x86 processor can multiply two 32-bit values and produce a 64-bit result.

5.2.2 Faster Multiplication by the "Comba" Method

One of the huge drawbacks of the "baseline" algorithms is that at the $O(n^2)$ level the carry must be computed and propagated upwards. This makes the nested loop very sequential and hard to unroll and implement in parallel. The "Comba" [4] method is named after little known (in cryptographic venues) Paul G. Comba who described a method of implementing fast multipliers that do not require nested carry fixup operations. As an interesting aside it seems that Paul Barrett describes a similar technique in his 1986 paper [7] written five years before.

At the heart of the Comba technique is once again the long-hand algorithm. Except in this case a slight twist is placed on how the columns of the result are produced. In the standard long-hand algorithm rows of products are produced then added together to form the final result. In the baseline algorithm the columns are added together after each iteration to get the result instantaneously.

In the Comba algorithm the columns of the result are produced entirely independently of each other. That is at the $O(n^2)$ level a simple multiplication and addition step is performed. The carries of the columns are propagated after the nested loop to reduce the amount of work required. Succintly the first step of the algorithm is to compute the product vector \vec{x} as follows.

$$\vec{x}_n = \sum_{i+j=n} a_i b_j, \forall n \in \{0, 1, 2, \dots, i+j\}$$
(5.1)

Where \vec{x}_n is the n'th column of the output vector. Consider the following example which computes the vector \vec{x} for the multiplication of 576 and 241.

		5	7	6	First Input
×		2	4	1	Second Input
		$1 \cdot 5 = 5$	$1 \cdot 7 = 7$	$1 \cdot 6 = 6$	First pass
	$4 \cdot 5 = 20$	$4 \cdot 7 + 5 = 33$	$4 \cdot 6 + 7 = 31$	6	Second pass
$2 \cdot 5 = 10$	$2 \cdot 7 + 20 = 34$	$2 \cdot 6 + 33 = 45$	31	6	Third pass
10	34	45	31	6	Final Result

Figure 5.3: Comba Multiplication Diagram

At this point the vector $x = \langle 10, 34, 45, 31, 6 \rangle$ is the result of the first step of the Comba multipler. Now the columns must be fixed by propagating the carry upwards. The resultant vector will have one extra dimension over the input vector which is congruent to adding a leading zero digit.

```
Algorithm Comba Fixup.

Input. Vector \vec{x} of dimension k

Output. Vector \vec{x} such that the carries have been propagated.
```

```
1. for n from 0 to k-1 do

1.1 \vec{x}_{n+1} \leftarrow \vec{x}_{n+1} + \lfloor \vec{x}_n/\beta \rfloor

1.2 \vec{x}_n \leftarrow \vec{x}_n \pmod{\beta}

2. Return(\vec{x}).
```

Figure 5.4: Algorithm Comba Fixup

With that algorithm and k = 5 and $\beta = 10$ the following vector is produced $\vec{x} = \langle 1, 3, 8, 8, 1, 6 \rangle$. In this case $241 \cdot 576$ is in fact 138816 and the procedure succeeded. If the algorithm is correct and as will be demonstrated shortly more efficient than the baseline algorithm why not simply always use this algorithm?

Column Weight.

At the nested $O(n^2)$ level the Comba method adds the product of two single precision variables to each column of the output independently. A serious obstacle is if the carry is lost, due to lack of precision before the algorithm has a chance to fix the carries. For example, in the multiplication of two three-digit numbers the third column of output will be the sum of three single precision multiplications. If the precision of the accumulator for the output digits is less then $3 \cdot (\beta - 1)^2$ then an overflow can occur and the carry information will be lost.

For any m and n digit inputs the maximum weight of any column is min(m, n) which is fairly obvious.

The maximum number of terms in any column of a product is known as the "column weight" and strictly governs when the algorithm can be used. Recall from earlier that a double precision type has α bits of resolution and a single precision digit has $lg(\beta)$ bits of precision. Given these two quantities we must not violate the following

$$k \cdot (\beta - 1)^2 < 2^{\alpha} \tag{5.2}$$

Which reduces to

$$k \cdot (\beta^2 - 2\beta + 1) < 2^{\alpha} \tag{5.3}$$

Let $\rho = lg(\beta)$ represent the number of bits in a single precision digit. By further re-arrangement of the equation the final solution is found.

$$k < \frac{2^{\alpha}}{(2^{2\rho} - 2^{\rho+1} + 1)} \tag{5.4}$$

The defaults for LibTomMath are $\beta=2^{28}$ and $\alpha=2^{64}$ which means that k is bounded by k<257. In this configuration the smaller input may not have more than 256 digits if the Comba method is to be used. This is quite satisfactory for most applications since 256 digits would allow for numbers in the range of $0 \le x < 2^{7168}$ which, is much larger than most public key cryptographic algorithms require.

Algorithm fast_s_mp_mul_digs.

```
Input. mp_int a, mp_int b and an integer digs
Output. c \leftarrow |a| \cdot |b| \pmod{\beta^{digs}}.
Place an array of MP_WARRAY double precision digits named \hat{W} on the stack.
1. If c.alloc < digs then grow c to digs digits. (mp\_grow)
2. If step 1 failed return (MP\_MEM).
Zero the temporary array \hat{W}.
3. for n from 0 to digs - 1 do
  3.1 \ \hat{W}_n \leftarrow 0
Compute the columns.
4. for ix from 0 to a.used - 1 do
  4.1 \ pb \leftarrow \min(b.used, digs - ix)
  4.2 If pb < 1 then goto step 5.
  4.3 for iy from 0 to pb - 1 do
     4.3.1 \ \hat{W}_{ix+iy} \leftarrow \hat{W}_{ix+iy} + a_{ix}b_{iy}
Propagate the carries upwards.
5. oldused \leftarrow c.used
6. c.used \leftarrow digs
7. If digs > 1 then do
  7.1. for ix from 1 to digs - 1 do
     7.1.1 \ \hat{W}_{ix} \leftarrow \hat{W}_{ix} + |\hat{W}_{ix-1}/\beta|
     7.1.2 \ c_{ix-1} \leftarrow \hat{W}_{ix-1} \pmod{\beta}
8. else do
  8.1~ix \leftarrow 0
9. c_{ix} \leftarrow \hat{W}_{ix} \pmod{\beta}
Zero excess digits.
10. If digs < oldused then do
  10.1 for n from digs to oldused-1 do
     10.1.1 c_n \leftarrow 0
11. Clamp excessive digits of c. (mp\_clamp)
12. Return(MP\_OKAY).
```

Figure 5.5: Algorithm fast_s_mp_mul_digs

Algorithm fast_s_mp_mul_digs. This algorithm performs the unsigned

multiplication of a and b using the Comba method limited to digs digits of precision. The algorithm essentially performs the same calculation as algorithm s_mp_mul_digs, just much faster.

The array \hat{W} is meant to be on the stack when the algorithm is used. The size of the array does not change which is ideal. Note also that unlike algorithm s_mp_mul_digs no temporary mp_int is required since the result is calculated directly in \hat{W} .

The $O(n^2)$ loop on step four is where the Comba method's advantages begin to show through in comparison to the baseline algorithm. The lack of a carry variable or propagation in this loop allows the loop to be performed with only single precision multiplication and additions. Now that each iteration of the inner loop can be performed independent of the others the inner loop can be performed with a high level of parallelism.

To measure the benefits of the Comba method over the baseline method consider the number of operations that are required. If the cost in terms of time of a multiply and addition is p and the cost of a carry propagation is q then a baseline multiplication would require $O\left((p+q)n^2\right)$ time to multiply two n-digit numbers. The Comba method requires only $O(pn^2+qn)$ time, however in practice, the speed increase is actually much more. With O(n) space the algorithm can be reduced to O(pn+qn) time by implementing the n multiply and addition operations in the nested loop in parallel.

```
File: bn_fast_s_mp_mul_digs.c
016
017
      /* Fast (comba) multiplier
018
019
       * This is the fast column-array [comba] multiplier.
020
       * designed to compute the columns of the product first
021
       * then handle the carries afterwards. This has the effect
022
       * of making the nested loops that compute the columns very
023
       * simple and schedulable on super-scalar processors.
024
025
       * This has been modified to produce a variable number of
026
       * digits of output so if say only a half-product is required
027
       * you don't have to compute the upper half (a feature
       * required for fast Barrett reduction).
028
029
030
       * Based on Algorithm 14.12 on pp.595 of HAC.
031
032
       */
033
      int
```

```
034
      fast_s_mp_mul_digs (mp_int * a, mp_int * b, mp_int * c, int digs)
035
036
                olduse, res, pa, ix;
        int
037
        mp_word W[MP_WARRAY];
038
039
        /* grow the destination as required */
        if (c->alloc < digs) {</pre>
040
          if ((res = mp_grow (c, digs)) != MP_OKAY) {
041
042
            return res;
043
044
045
046
        /* clear temp buf (the columns) */
047
        memset (W, 0, sizeof (mp_word) * digs);
048
049
        /* calculate the columns */
050
        pa = a->used;
051
        for (ix = 0; ix < pa; ix++) \{
052
          /* this multiplier has been modified to allow you to
053
           * control how many digits of output are produced.
           * So at most we want to make upto "digs" digits of output.
054
055
056
           * this adds products to distinct columns (at ix+iy) of W
           * note that each step through the loop is not dependent on
057
           * the previous which means the compiler can easily unroll
058
059
           * the loop without scheduling problems
060
           */
061
062
            register mp_digit tmpx, *tmpy;
063
            register mp_word *_W;
            register int iy, pb;
064
065
066
            /* alias for the the word on the left e.g. A[ix] * A[iy] */
067
            tmpx = a->dp[ix];
068
            /* alias for the right side */
069
070
            tmpy = b->dp;
071
072
            /* alias for the columns, each step through the loop adds a new
073
               term to each column
074
             */
075
            _W = W + ix;
```

```
076
077
            /* the number of digits is limited by their placement. E.g.
078
               we avoid multiplying digits that will end up above the # of
079
               digits of precision requested
080
081
            pb = MIN (b->used, digs - ix);
082
            for (iy = 0; iy < pb; iy++) \{
083
084
              *_W++ += ((mp_word)tmpx) * ((mp_word)*tmpy++);
085
086
087
088
        }
089
090
        /* setup dest */
091
        olduse = c->used;
092
        c->used = digs;
093
094
095
          register mp_digit *tmpc;
096
097
          /* At this point W[] contains the sums of each column. To get the
098
           st correct result we must take the extra bits from each column and
099
           * carry them down
100
101
           * Note that while this adds extra code to the multiplier it
102
           * saves time since the carry propagation is removed from the
           * above nested loop. This has the effect of reducing the work
103
104
           * from N*(N+N*c)==N**2 + c*N**2 to N**2 + N*c where c is the
105
           * cost of the shifting. On very small numbers this is slower
106
           * but on most cryptographic size numbers it is faster.
107
108
           * In this particular implementation we feed the carries from
109
           * behind which means when the loop terminates we still have one
           * last digit to copy
110
111
           */
112
          tmpc = c->dp;
113
          for (ix = 1; ix < digs; ix++) \{
            /* forward the carry from the previous temp */
114
            W[ix] += (W[ix - 1] >> ((mp\_word) DIGIT\_BIT));
115
116
117
            /* now extract the previous digit [below the carry] */
```

```
*tmpc++ = (mp_digit) (W[ix - 1] & ((mp_word) MP_MASK));
118
          }
119
          /* fetch the last digit */
120
121
          *tmpc++ = (mp_digit) (W[digs - 1] & ((mp_word) MP_MASK));
122
          /* clear unused digits [that existed in the old copy of c] */
123
124
          for (; ix < olduse; ix++) {</pre>
            *tmpc++ = 0;
125
126
127
128
        mp_clamp (c);
        return MP_OKAY;
129
130
      }
```

The memset on line 47 clears the initial \hat{W} array to zero in a single step. Like the slower baseline multiplication implementation a series of aliases (lines 67, 70 and 75) are used to simplify the inner $O(n^2)$ loop. In this case a new alias $_{\hat{W}}$ has been added which refers to the double precision columns offset by ix in each pass.

The inner loop on lines 83, 84 and 85 is where the algorithm will spend the majority of the time, which is why it has been stripped to the bones of any extra baggage². On x86 processors the multiplication and additions amount to at the very least five instructions (two loads, two additions, one multiply) while on the ARMv4 processors they amount to only three (one load, one store, one multiply-add). For both of the x86 and ARMv4 processors the GCC compiler performs a good job at unrolling the loop and scheduling the instructions so there are very few dependency stalls.

In theory the difference between the baseline and comba algorithms is a mere O(qn) time difference. However, in the $O(n^2)$ nested loop of the baseline method there are dependency stalls as the algorithm must wait for the multiplier to finish before propagating the carry to the next digit. As a result fewer of the often multiple execution units³ can be simultaneously used.

5.2.3 Polynomial Basis Multiplication

To break the $O(n^2)$ barrier in multiplication requires a completely different look at integer multiplication. In the following algorithms the use of polynomial basis representation for two integers a and b as $f(x) = \sum_{i=0}^{n} a_i x^i$ and $g(x) = \sum_{i=0}^{n} a_i x^i$

²Hence the pointer aliases.

³The AMD Athlon has three execution units and the Intel P4 has four.

 $\sum_{i=0}^{n} b_i x^i$ respectively, is required. In this system both f(x) and g(x) have n+1 terms and are of the n'th degree.

The product $a \cdot b \equiv f(x)g(x)$ is the polynomial $W(x) = \sum_{i=0}^{2n} w_i x^i$. The coefficients w_i will directly yield the desired product when β is substituted for x. The direct solution to solve for the 2n+1 coefficients requires $O(n^2)$ time and would in practice be slower than the Comba technique.

However, numerical analysis theory indicates that only 2n+1 distinct points in W(x) are required to determine the values of the 2n+1 unknown coefficients. This means by finding $\zeta_y = W(y)$ for 2n+1 small values of y the coefficients of W(x) can be found with Gaussian elimination. This technique is also occasionally referred to as the *interpolation technique* (references please...) since in effect an interpolation based on 2n+1 points will yield a polynomial equivalent to W(x).

The coefficients of the polynomial W(x) are unknown which makes finding W(y) for any value of y impossible. However, since W(x) = f(x)g(x) the equivalent $\zeta_y = f(y)g(y)$ can be used in its place. The benefit of this technique stems from the fact that f(y) and g(y) are much smaller than either a or b respectively. As a result finding the 2n + 1 relations required by multiplying f(y)g(y) involves multiplying integers that are much smaller than either of the inputs.

When picking points to gather relations there are always three obvious points to choose, y=0,1 and ∞ . The ζ_0 term is simply the product $W(0)=w_0=a_0\cdot b_0$. The ζ_1 term is the product $W(1)=(\sum_{i=0}^n a_i)(\sum_{i=0}^n b_i)$. The third point ζ_∞ is less obvious but rather simple to explain. The 2n+1'th coefficient of W(x) is numerically equivalent to the most significant column in an integer multiplication. The point at ∞ is used symbolically to represent the most significant column, that is $W(\infty)=w_{2n}=a_nb_n$. Note that the points at y=0 and ∞ yield the coefficients w_0 and w_{2n} directly.

If more points are required they should be of small values and powers of two such as 2^q and the related *mirror points* $(2^q)^{2n} \cdot \zeta_{2^{-q}}$ for small values of q. The term "mirror point" stems from the fact that $(2^q)^{2n} \cdot \zeta_{2^{-q}}$ can be calculated in the exact opposite fashion as ζ_{2^q} . For example, when n=2 and q=1 then following two equations are equivalent to the point ζ_2 and its mirror.

$$\zeta_2 = f(2)g(2) = (4a_2 + 2a_1 + a_0)(4b_2 + 2b_1 + b_0)$$

$$16 \cdot \zeta_{\frac{1}{2}} = 4f(\frac{1}{2}) \cdot 4g(\frac{1}{2}) = (a_2 + 2a_1 + 4a_0)(b_2 + 2b_1 + 4b_0)$$
(5.5)

Using such points will allow the values of f(y) and g(y) to be independently

Split into n Parts	Exponent	Notes
2	1.584962501	This is Karatsuba Multiplication.
3	1.464973520	This is Toom-Cook Multiplication.
4	1.403677461	
5	1.365212389	
10	1.278753601	
100	1.149426538	
1000	1.100270931	
10000	1.075252070	

Figure 5.6: Asymptotic Running Time of Polynomial Basis Multiplication

calculated using only left shifts. For example, when n = 2 the polynomial $f(2^q)$ is equal to $2^q((2^q a_2) + a_1) + a_0$. This technique of polynomial representation is known as Horner's method.

As a general rule of the algorithm when the inputs are split into n parts each there are 2n-1 multiplications. Each multiplication is of multiplicands that have n times fewer digits than the inputs. The asymptotic running time of this algorithm is $O\left(k^{lg_n(2n-1)}\right)$ for k digit inputs (assuming they have the same number of digits). Figure 5.6 summarizes the exponents for various values of n.

At first it may seem like a good idea to choose n=1000 since the exponent is approximately 1.1. However, the overhead of solving for the 2001 terms of W(x) will certainly consume any savings the algorithm could offer for all but exceedingly large numbers.

Cutoff Point

The polynomial basis multiplication algorithms all require fewer single precision multiplications than a straight Comba approach. However, the algorithms incur an overhead (at the O(n) work level) since they require a system of equations to be solved. This makes the polynomial basis approach more costly to use with small inputs.

Let m represent the number of digits in the multiplicands (assume both multiplicands have the same number of digits). There exists a point y such that when m < y the polynomial basis algorithms are more costly than Comba, when m = y they are roughly the same cost and when m > y the Comba methods are slower than the polynomial basis algorithms.

The exact location of y depends on several key architectural elements of the computer platform in question.

- 1. The ratio of clock cycles for single precision multiplication versus other simpler operations such as addition, shifting, etc. For example on the AMD Athlon the ratio is roughly 17:1 while on the Intel P4 it is 29:1. The higher the ratio in favour of multiplication the lower the cutoff point y will be.
- 2. The complexity of the linear system of equations (for the coefficients of W(x)) is. Generally speaking as the number of splits grows the complexity grows substantially. Ideally solving the system will only involve addition, subtraction and shifting of integers. This directly reflects on the ratio previous mentioned.
- 3. To a lesser extent memory bandwidth and function call overheads. Provided the values are in the processor cache this is less of an influence over the cutoff point.

A clean cutoff point separation occurs when a point y is found such that all of the cutoff point conditions are met. For example, if the point is too low then there will be values of m such that m > y and the Comba method is still faster. Finding the cutoff points is fairly simple when a high resolution timer is available.

5.2.4 Karatsuba Multiplication

Karatsuba [5] multiplication when originally proposed in 1962 was among the first set of algorithms to break the $O(n^2)$ barrier for general purpose multiplication. Given two polynomial basis representations f(x) = ax + b and g(x) = cx + d, Karatsuba proved with light algebra [6] that the following polynomial is equivalent to multiplication of the two integers the polynomials represent.

$$f(x) \cdot g(x) = acx^{2} + ((a-b)(c-d) + ac + bd)x + bd$$
 (5.6)

Using the observation that ac and bd could be re-used only three half sized multiplications would be required to produce the product. Applying this algorithm recursively, the work factor becomes $O(n^{lg(3)})$ which is substantially better than the work factor $O(n^2)$ of the Comba technique. It turns out what

Karatsuba did not know or at least did not publish was that this is simply polynomial basis multiplication with the points ζ_0 , ζ_{∞} and $-\zeta_{-1}$. Consider the resultant system of equations.

$$\begin{array}{rclcrcl}
\zeta_0 & = & & & w_0 \\
-\zeta_{-1} & = & -w_2 & + & w_1 & - & w_0 \\
\zeta_{\infty} & = & w_2
\end{array}$$

By adding the first and last equation to the equation in the middle the term w_1 can be isolated and all three coefficients solved for. The simplicity of this system of equations has made Karatsuba fairly popular. In fact the cutoff point is often fairly low⁴ making it an ideal algorithm to speed up certain public key cryptosystems such as RSA and Diffie-Hellman. It is worth noting that the point ζ_1 could be substituted for $-\zeta_{-1}$. In this case the first and third row are subtracted instead of added to the second row.

 $^{^4}$ With LibTomMath 0.18 it is 70 and 109 digits for the Intel P4 and AMD Athlon respectively.

```
Algorithm mp_karatsuba_mul.
Input. mp_int a and mp_int b
Output. c \leftarrow |a| \cdot |b|
1. Init the following mp_int variables: x0, x1, y0, y1, t1, x0y0, x1y1.
2. If step 2 failed then return(MP\_MEM).
Split the input. e.g. a = x1 \cdot \beta^B + x0
3. B \leftarrow \min(a.used, b.used)/2
4. x0 \leftarrow a \pmod{\beta^B} \pmod{2d}
5. y0 \leftarrow b \pmod{\beta^B}
6. x1 \leftarrow \lfloor a/\beta^B \rfloor \ (mp\_rshd)
7. y1 \leftarrow \lfloor b/\beta^B \rfloor
Calculate the three products.
8. x0y0 \leftarrow x0 \cdot y0 \ (mp\_mul)
9. x1y1 \leftarrow x1 \cdot y1
10. t1 \leftarrow x1 - x0 \ (mp\_sub)
11. x0 \leftarrow y1 - y0
12. t1 \leftarrow t1 \cdot x0
Calculate the middle term.
13. x0 \leftarrow x0y0 + x1y1
14. t1 \leftarrow x0 - t1
Calculate the final product.
15. t1 \leftarrow t1 \cdot \beta^B \ (mp\_lshd)
16. x1y1 \leftarrow x1y1 \cdot \beta^{2B}
17. t1 \leftarrow x0y0 + t1
18. c \leftarrow t1 + x1y1
19. Clear all of the temporary variables.
20. Return(MP\_OKAY).
```

Figure 5.7: Algorithm mp_karatsuba_mul

Algorithm mp_karatsuba_mul. This algorithm computes the unsigned product of two inputs using the Karatsuba multiplication algorithm. It is loosely based on the description from Knuth [1, pp. 294-295].

In order to split the two inputs into their respective halves, a suitable *radix* point must be chosen. The radix point chosen must be used for both of the

inputs meaning that it must be smaller than the smallest input. Step 3 chooses the radix point B as half of the smallest input **used** count. After the radix point is chosen the inputs are split into lower and upper halves. Step 4 and 5 compute the lower halves. Step 6 and 7 computer the upper halves.

After the halves have been computed the three intermediate half-size products must be computed. Step 8 and 9 compute the trivial products $x0 \cdot y0$ and $x1 \cdot y1$. The mp_int x0 is used as a temporary variable after x1 - x0 has been computed. By using x0 instead of an additional temporary variable, the algorithm can avoid an addition memory allocation operation.

The remaining steps 13 through 18 compute the Karatsuba polynomial through a variety of digit shifting and addition operations.

```
File: bn_mp_karatsuba_mul.c
017
      /* c = |a| * |b| using Karatsuba Multiplication using
018
       * three half size multiplications
019
020
       * Let B represent the radix [e.g. 2**DIGIT_BIT] and
       * let n represent half of the number of digits in
021
022
       * the min(a,b)
023
024
       * a = a1 * B**n + a0
025
       * b = b1 * B**n + b0
026
027
       * Then, a * b =>
         a1b1 * B**2n + ((a1 - a0)(b1 - b0) + a0b0 + a1b1) * B + a0b0
028
029
030
       * Note that a1b1 and a0b0 are used twice and only need to be
031
       * computed once. So in total three half size (half # of
032
       * digit) multiplications are performed, a0b0, a1b1 and
033
       * (a1-b1)(a0-b0)
034
035
       * Note that a multiplication of half the digits requires
036
       * 1/4th the number of single precision multiplications so in
037
       * total after one call 25% of the single precision multiplications
038
       * are saved. Note also that the call to mp_mul can end up back
039
       * in this function if the a0, a1, b0, or b1 are above the threshold.
040
       * This is known as divide-and-conquer and leads to the famous
041
       * O(N**lg(3)) or O(N**1.584) work which is asymptopically lower than
042
       * the standard O(N**2) that the baseline/comba methods use.
043
       * Generally though the overhead of this method doesn't pay off
044
       * until a certain size (N ~ 80) is reached.
```

```
045
       */
046
      int
047
      mp_karatsuba_mul (mp_int * a, mp_int * b, mp_int * c)
048
049
        mp_int x0, x1, y0, y1, t1, x0y0, x1y1;
050
        int
                B, err;
051
052
        /* default the return code to an error */
053
        err = MP_MEM;
054
055
        /* min # of digits */
056
        B = MIN (a->used, b->used);
057
058
        /* now divide in two */
059
        B = B / 2;
060
061
        /* init copy all the temps */
062
        if (mp_init_size (&x0, B) != MP_OKAY)
063
          goto ERR;
064
        if (mp_init_size (&x1, a->used - B) != MP_OKAY)
065
          goto X0;
        if (mp_init_size (&y0, B) != MP_OKAY)
066
067
          goto X1;
        if (mp_init_size (&y1, b->used - B) != MP_OKAY)
068
069
          goto YO;
070
071
        /* init temps */
072
        if (mp_init_size (&t1, B * 2) != MP_OKAY)
073
          goto Y1;
074
        if (mp_init_size (&x0y0, B * 2) != MP_OKAY)
075
          goto T1;
076
        if (mp_init_size (&x1y1, B * 2) != MP_OKAY)
077
          goto XOYO;
078
079
        /* now shift the digits */
080
        x0.sign = x1.sign = a->sign;
081
        y0.sign = y1.sign = b->sign;
082
083
        x0.used = y0.used = B;
084
        x1.used = a->used - B;
085
        y1.used = b->used - B;
086
```

```
087
880
          register int x;
089
          register mp_digit *tmpa, *tmpb, *tmpx, *tmpy;
090
091
          /* we copy the digits directly instead of using higher level functions
           * since we also need to shift the digits
092
093
           */
094
          tmpa = a->dp;
095
          tmpb = b->dp;
096
097
          tmpx = x0.dp;
098
          tmpy = y0.dp;
099
          for (x = 0; x < B; x++) {
            *tmpx++ = *tmpa++;
100
101
            *tmpy++ = *tmpb++;
102
103
104
          tmpx = x1.dp;
105
          for (x = B; x < a-)used; x++) {
            *tmpx++ = *tmpa++;
106
107
108
109
          tmpy = y1.dp;
          for (x = B; x < b-)used; x++) {
110
            *tmpy++ = *tmpb++;
111
          }
112
113
        }
114
115
        /* only need to clamp the lower words since by definition the
116
         * upper words x1/y1 must have a known number of digits
         */
117
118
        mp_clamp (&x0);
119
        mp_clamp (&y0);
120
121
        /* now calc the products x0y0 and x1y1 */
122
        /* after this x0 is no longer required, free temp [x0==t2]! */
        if (mp_mul (&x0, &y0, &x0y0) != MP_OKAY)
123
          goto X1Y1;
124
                              /* x0y0 = x0*y0 */
        if (mp_mul (&x1, &y1, &x1y1) != MP_OKAY)
125
          goto X1Y1;
                              /* x1y1 = x1*y1 */
126
127
128
        /* now calc x1-x0 and y1-y0 */
```

```
if (mp_sub (&x1, &x0, &t1) != MP_OKAY)
129
130
          goto X1Y1;
                              /* t1 = x1 - x0 */
        if (mp_sub (&y1, &y0, &x0) != MP_OKAY)
131
132
          goto X1Y1;
                              /* t2 = y1 - y0 */
133
        if (mp_mul (&t1, &x0, &t1) != MP_OKAY)
134
          goto X1Y1;
                              /* t1 = (x1 - x0) * (y1 - y0) */
135
136
        /* add x0y0 */
        if (mp_add (&x0y0, &x1y1, &x0) != MP_OKAY)
137
138
          goto X1Y1;
                              /* t2 = x0y0 + x1y1 */
        if (mp_sub (&x0, &t1, &t1) != MP_OKAY)
139
                              /* t1 = x0y0 + x1y1 - (x1-x0)*(y1-y0) */
140
          goto X1Y1;
141
        /* shift by B */
142
143
        if (mp_lshd (&t1, B) != MP_OKAY)
144
          goto X1Y1;
                              /* t1 = (x0y0 + x1y1 - (x1-x0)*(y1-y0)) << B */
145
        if (mp_1shd (&x1y1, B * 2) != MP_0KAY)
146
          goto X1Y1;
                              /* x1y1 = x1y1 << 2*B */
147
148
        if (mp_add (&x0y0, &t1, &t1) != MP_OKAY)
149
          goto X1Y1;
                              /* t1 = x0y0 + t1 */
150
        if (mp_add (&t1, &x1y1, c) != MP_OKAY)
                              /* t1 = x0y0 + t1 + x1y1 */
151
          goto X1Y1;
152
153
        /* Algorithm succeeded set the return code to MP_OKAY */
        err = MP_OKAY;
154
155
156
     X1Y1:mp_clear (&x1y1);
157
     XOYO:mp_clear (&xOyO);
158
     T1:mp_clear (&t1);
159
     Y1:mp_clear (&y1);
160
     Y0:mp_clear (&y0);
161
     X1:mp_clear (&x1);
162
     X0:mp_clear (&x0);
163
     ERR:
164
        return err;
165
```

The new coding element in this routine, not seen in previous routines, is the usage of goto statements. The conventional wisdom is that goto statements should be avoided. This is generally true, however when every single function call can fail, it makes sense to handle error recovery with a single piece of code. Lines 62 to 76 handle initializing all of the temporary variables required. Note how each of the if statements goes to a different label in case of failure. This allows the routine to correctly free only the temporaries that have been successfully allocated so far.

The temporary variables are all initialized using the mp_init_size routine since they are expected to be large. This saves the additional reallocation that would have been necessary. Also x0, x1, y0 and y1 have to be able to hold at least their respective number of digits for the next section of code.

The first algebraic portion of the algorithm is to split the two inputs into their halves. However, instead of using mp_mod_2d and mp_rshd to extract the halves, the respective code has been placed inline within the body of the function. To initialize the halves, the **used** and **sign** members are copied first. The first for loop on line 99 copies the lower halves. Since they are both the same magnitude it is simpler to calculate both lower halves in a single loop. The for loop on lines 105 and 110 calculate the upper halves x1 and y1 respectively.

By inlining the calculation of the halves, the Karatsuba multiplier has a slightly lower overhead and can be used for smaller magnitude inputs.

When line 154 is reached, the algorithm has completed successfully. The "error status" variable *err* is set to **MP_OKAY** so that the same code that handles errors can be used to clear the temporary variables and return.

5.2.5 Toom-Cook 3-Way Multiplication

Toom-Cook 3-Way [?] multiplication is essentially the polynomial basis algorithm for n=2 except that the points are chosen such that ζ is easy to compute and the resulting system of equations easy to reduce. Here, the points ζ_0 , $16 \cdot \zeta_{\frac{1}{2}}$, ζ_1 , ζ_2 and ζ_{∞} make up the five required points to solve for the coefficients of the W(x).

With the five relations that Toom-Cook specifies, the following system of equations is formed.

A trivial solution to this matrix requires 12 subtractions, two multiplications by a small power of two, two divisions by a small power of two, two divisions by three and one multiplication by three. All of these 19 sub-operations require less than quadratic time, meaning that the algorithm can be faster than a baseline multiplication. However, the greater complexity of this algorithm places the cutoff point (**TOOM_MUL_CUTOFF**) where Toom-Cook becomes more efficient much higher than the Karatsuba cutoff point.

```
Algorithm mp_toom_mul.
Input. mp_int a and mp_int b
Output. c \leftarrow a \cdot b
Split a and b into three pieces. E.g. a = a_2 \beta^{2k} + a_1 \beta^k + a_0
1. k \leftarrow |\min(a.used, b.used)/3|
2. a_0 \leftarrow a \pmod{\beta^k}
3. a_1 \leftarrow \lfloor a/\beta^k \rfloor, a_1 \leftarrow a_1 \pmod{\beta^k}
4. a_2 \leftarrow \lfloor a/\beta^{2k} \rfloor, a_2 \leftarrow a_2 \pmod{\beta^k}
5. b_0 \leftarrow a \pmod{\beta^k}
6. b_1 \leftarrow \lfloor a/\beta^k \rfloor, b_1 \leftarrow b_1 \pmod{\beta^k}
7. b_2 \leftarrow \lfloor a/\beta^{2k} \rfloor, b_2 \leftarrow b_2 \pmod{\beta^k}
Find the five equations for w_0, w_1, ..., w_4.
8. w_0 \leftarrow a_0 \cdot b_0
9. w_4 \leftarrow a_2 \cdot b_2
10. tmp_1 \leftarrow 2 \cdot a_0, tmp_1 \leftarrow a_1 + tmp_1, tmp_1 \leftarrow 2 \cdot tmp_1, tmp_1 \leftarrow tmp_1 + a_2
11. tmp_2 \leftarrow 2 \cdot b_0, tmp_2 \leftarrow b_1 + tmp_2, tmp_2 \leftarrow 2 \cdot tmp_2, tmp_2 \leftarrow tmp_2 + b_2
12. w_1 \leftarrow tmp_1 \cdot tmp_2
13. tmp_1 \leftarrow 2 \cdot a_2, tmp_1 \leftarrow a_1 + tmp_1, tmp_1 \leftarrow 2 \cdot tmp_1, tmp_1 \leftarrow tmp_1 + a_0
14. tmp_2 \leftarrow 2 \cdot b_2, tmp_2 \leftarrow b_1 + tmp_2, tmp_2 \leftarrow 2 \cdot tmp_2, tmp_2 \leftarrow tmp_2 + b_0
15. w_3 \leftarrow tmp_1 \cdot tmp_2
16. tmp_1 \leftarrow a_0 + a_1, tmp_1 \leftarrow tmp_1 + a_2, tmp_2 \leftarrow b_0 + b_1, tmp_2 \leftarrow tmp_2 + b_2
17. w_2 \leftarrow tmp_1 \cdot tmp_2
Continued on the next page.
```

Figure 5.8: Algorithm mp_toom_mul

```
Algorithm mp_toom_mul (continued).
Input. mp_int a and mp_int b
Output. c \leftarrow a \cdot b
Now solve the system of equations.
18. w_1 \leftarrow w_4 - w_1, w_3 \leftarrow w_3 - w_0
19. w_1 \leftarrow |w_1/2|, w_3 \leftarrow |w_3/2|
20. w_2 \leftarrow w_2 - w_0, w_2 \leftarrow w_2 - w_4
21. w_1 \leftarrow w_1 - w_2, w_3 \leftarrow w_3 - w_2
22. tmp_1 \leftarrow 8 \cdot w_0, w_1 \leftarrow w_1 - tmp_1, tmp_1 \leftarrow 8 \cdot w_4, w_3 \leftarrow w_3 - tmp_1
23. w_2 \leftarrow 3 \cdot w_2, w_2 \leftarrow w_2 - w_1, w_2 \leftarrow w_2 - w_3
24. w_1 \leftarrow w_1 - w_2, w_3 \leftarrow w_3 - w_2
25. w_1 \leftarrow |w_1/3|, w_3 \leftarrow |w_3/3|
Now substitute \beta^k for x by shifting w_0, w_1, ..., w_4.
26. for n from 1 to 4 do
  26.1 \ w_n \leftarrow w_n \cdot \beta^{nk}
27. c \leftarrow w_0 + w_1, c \leftarrow c + w_2, c \leftarrow c + w_3, c \leftarrow c + w_4
28. Return(MP\_OKAY)
```

Figure 5.9: Algorithm mp_toom_mul (continued)

Algorithm mp_toom_mul. This algorithm computes the product of two mp_int variables a and b using the Toom-Cook approach. Compared to the Karatsuba multiplication, this algorithm has a lower asymptotic running time of approximately $O(n^{1.464})$ but at an obvious cost in overhead. In this description, several statements have been compounded to save space. The intention is that the statements are executed from left to right across any given step.

The two inputs a and b are first split into three k-digit integers a_0, a_1, a_2 and b_0, b_1, b_2 respectively. From these smaller integers the coefficients of the polynomial basis representations f(x) and g(x) are known and can be used to find the relations required.

The first two relations w_0 and w_4 are the points ζ_0 and ζ_∞ respectively. The relation w_1, w_2 and w_3 correspond to the points $16 \cdot \zeta_{\frac{1}{2}}, \zeta_2$ and ζ_1 respectively. These are found using logical shifts to independently find f(y) and g(y) which significantly speeds up the algorithm.

After the five relations w_0, w_1, \ldots, w_4 have been computed, the system they represent must be solved in order for the unknown coefficients w_1, w_2 and w_3 to be isolated. The steps 18 through 25 perform the system reduction required

as previously described. Each step of the reduction represents the comparable matrix operation that would be performed had this been performed by pencil. For example, step 18 indicates that row 1 must be subtracted from row 4 and simultaneously row 0 subtracted from row 3.

Once the coefficients have been isolated, the polynomial $W(x) = \sum_{i=0}^{2n} w_i x^i$ is known. By substituting β^k for x, the integer result $a \cdot b$ is produced.

```
File: bn_mp_toom_mul.c
016
017
      /* multiplication using the Toom-Cook 3-way algorithm */
018
      mp_toom_mul(mp_int *a, mp_int *b, mp_int *c)
019
020
021
          mp_int w0, w1, w2, w3, w4, tmp1, tmp2, a0, a1, a2, b0, b1, b2;
022
          int res, B;
023
          /* init temps */
024
025
          if ((res = mp_init_multi(&w0, &w1, &w2, &w3, &w4,
                                    &a0, &a1, &a2, &b0, &b1,
026
                                    &b2, &tmp1, &tmp2, NULL)) != MP_OKAY) {
027
028
             return res;
029
          }
030
          /* B */
031
032
          B = MIN(a->used, b->used) / 3;
033
          /* a = a2 * B**2 + a1 * B + a0 */
034
          if ((res = mp_mod_2d(a, DIGIT_BIT * B, &a0)) != MP_OKAY) {
035
036
             goto ERR;
037
          }
038
          if ((res = mp_copy(a, &a1)) != MP_OKAY) {
039
040
             goto ERR;
041
042
          mp_rshd(&a1, B);
043
          mp_mod_2d(&a1, DIGIT_BIT * B, &a1);
044
045
          if ((res = mp_copy(a, &a2)) != MP_OKAY) {
             goto ERR;
046
047
048
          mp_rshd(&a2, B*2);
049
```

```
050
          /* b = b2 * B**2 + b1 * B + b0 */
051
          if ((res = mp_mod_2d(b, DIGIT_BIT * B, &b0)) != MP_OKAY) {
052
             goto ERR;
053
          }
054
          if ((res = mp_copy(b, &b1)) != MP_OKAY) {
055
             goto ERR;
056
057
058
          mp_rshd(&b1, B);
          mp_mod_2d(&b1, DIGIT_BIT * B, &b1);
059
060
          if ((res = mp_copy(b, &b2)) != MP_OKAY) {
061
062
             goto ERR;
063
064
          mp_rshd(&b2, B*2);
065
066
          /* w0 = a0*b0 */
067
          if ((res = mp_mul(&a0, &b0, &w0)) != MP_OKAY) {
             goto ERR;
068
069
          }
070
071
          /* w4 = a2 * b2 */
072
          if ((res = mp_mul(&a2, &b2, &w4)) != MP_OKAY) {
073
             goto ERR;
074
          }
075
076
          /* w1 = (a2 + 2(a1 + 2a0))(b2 + 2(b1 + 2b0)) */
077
          if ((res = mp_mul_2(&a0, &tmp1)) != MP_OKAY) {
078
             goto ERR;
079
080
          if ((res = mp_add(&tmp1, &a1, &tmp1)) != MP_OKAY) {
081
             goto ERR;
082
083
          if ((res = mp_mul_2(&tmp1, &tmp1)) != MP_OKAY) {
084
             goto ERR;
085
          }
          if ((res = mp_add(&tmp1, &a2, &tmp1)) != MP_OKAY) \{
086
087
             goto ERR;
088
          }
089
090
          if ((res = mp_mul_2(&b0, &tmp2)) != MP_OKAY) {
091
             goto ERR;
```

```
092
093
          if ((res = mp_add(&tmp2, &b1, &tmp2)) != MP_OKAY) {
094
             goto ERR;
095
096
          if ((res = mp_mul_2(&tmp2, &tmp2)) != MP_OKAY) {
097
             goto ERR;
098
099
          if ((res = mp_add(&tmp2, &b2, &tmp2)) != MP_OKAY) {
100
             goto ERR;
101
102
103
          if ((res = mp_mul(&tmp1, &tmp2, &w1)) != MP_OKAY) {
104
             goto ERR;
105
106
107
          /* w3 = (a0 + 2(a1 + 2a2))(b0 + 2(b1 + 2b2)) */
108
          if ((res = mp_mul_2(&a2, &tmp1)) != MP_OKAY) {
109
             goto ERR;
110
          if ((res = mp_add(&tmp1, &a1, &tmp1)) != MP_OKAY) {
111
112
             goto ERR;
113
          if ((res = mp_mul_2(&tmp1, &tmp1)) != MP_OKAY) {
114
             goto ERR;
115
116
          if ((res = mp_add(&tmp1, &a0, &tmp1)) != MP_OKAY) {
117
118
             goto ERR;
119
120
121
          if ((res = mp_mul_2(&b2, &tmp2)) != MP_OKAY) {
122
             goto ERR;
123
124
          if ((res = mp_add(&tmp2, &b1, &tmp2)) != MP_OKAY) {
125
             goto ERR;
126
127
          if ((res = mp_mul_2(&tmp2, &tmp2)) != MP_OKAY) {
             goto ERR;
128
129
          if ((res = mp_add(&tmp2, &b0, &tmp2)) != MP_OKAY) {
130
131
             goto ERR;
132
          }
133
```

```
if ((res = mp_mul(&tmp1, &tmp2, &w3)) != MP_OKAY) {
134
135
             goto ERR;
          }
136
137
138
          /* w2 = (a2 + a1 + a0)(b2 + b1 + b0) */
139
          if ((res = mp_add(&a2, &a1, &tmp1)) != MP_OKAY) {
140
             goto ERR;
141
142
          if ((res = mp_add(&tmp1, &a0, &tmp1)) != MP_OKAY) {
143
144
             goto ERR;
145
          }
          if ((res = mp_add(&b2, &b1, &tmp2)) != MP_OKAY) {
146
147
             goto ERR;
148
149
          if ((res = mp_add(&tmp2, &b0, &tmp2)) != MP_OKAY) {
150
             goto ERR;
151
152
          if ((res = mp_mul(&tmp1, &tmp2, &w2)) != MP_OKAY) {
153
             goto ERR;
154
155
156
          /* now solve the matrix
157
158
             0 0 0 0 1
159
             1 2 4 8 16
160
             1 1 1
                     1
             16 8 4 2 1
161
162
             1 0 0 0
163
164
            using 12 subtractions, 4 shifts,
165
                    2 small divisions and 1 small multiplication
166
           */
167
168
           /* r1 - r4 */
169
           if ((res = mp_sub(&w1, &w4, &w1)) != MP_OKAY) {
170
              goto ERR;
171
           /* r3 - r0 */
172
           if ((res = mp_sub(&w3, &w0, &w3)) != MP_OKAY) {
173
174
              goto ERR;
175
```

```
/* r1/2 */
176
177
           if ((res = mp_div_2(&w1, &w1)) != MP_OKAY) {
178
              goto ERR;
179
180
           /* r3/2 */
           if ((res = mp_div_2(&w3, &w3)) != MP_OKAY) {
181
182
              goto ERR;
183
           /* r2 - r0 - r4 */
184
           if ((res = mp_sub(&w2, &w0, &w2)) != MP_OKAY) {
185
186
              goto ERR;
187
           }
           if ((res = mp_sub(&w2, &w4, &w2)) != MP_OKAY) {
188
189
              goto ERR;
190
           }
191
           /* r1 - r2 */
192
           if ((res = mp_sub(&w1, &w2, &w1)) != MP_OKAY) {
193
              goto ERR;
194
           }
195
           /* r3 - r2 */
           if ((res = mp_sub(&w3, &w2, &w3)) != MP_OKAY) {
196
197
              goto ERR;
198
           /* r1 - 8r0 */
199
           if ((res = mp_mul_2d(&w0, 3, &tmp1)) != MP_OKAY) {
200
201
              goto ERR;
202
203
           if ((res = mp_sub(&w1, &tmp1, &w1)) != MP_OKAY) {
204
              goto ERR;
205
206
           /* r3 - 8r4 */
207
           if ((res = mp_mul_2d(&w4, 3, &tmp1)) != MP_OKAY) {
208
              goto ERR;
209
210
           if ((res = mp_sub(&w3, &tmp1, &w3)) != MP_OKAY) {
211
              goto ERR;
212
213
           /* 3r2 - r1 - r3 */
           if ((res = mp_mul_d(&w2, 3, &w2)) != MP_OKAY) {
214
215
              goto ERR;
216
217
           if ((res = mp_sub(&w2, &w1, &w2)) != MP_OKAY) {
```

```
218
              goto ERR;
219
220
           if ((res = mp_sub(&w2, &w3, &w2)) != MP_OKAY) {
221
              goto ERR;
222
           /* r1 - r2 */
223
           if ((res = mp_sub(&w1, &w2, &w1)) != MP_OKAY) {
224
              goto ERR;
225
226
227
           /* r3 - r2 */
           if ((res = mp_sub(&w3, &w2, &w3)) != MP_OKAY) {
228
229
              goto ERR;
230
           /* r1/3 */
231
232
           if ((res = mp_div_3(&w1, &w1, NULL)) != MP_OKAY) {
233
              goto ERR;
234
235
           /* r3/3 */
236
           if ((res = mp_div_3(&w3, &w3, NULL)) != MP_OKAY) {
237
              goto ERR;
238
239
240
           /* at this point shift W[n] by B*n */
           if ((res = mp_lshd(&w1, 1*B)) != MP_OKAY) {
241
242
              goto ERR;
243
           if ((res = mp_lshd(&w2, 2*B)) != MP_OKAY) {
244
245
              goto ERR;
246
247
           if ((res = mp_lshd(&w3, 3*B)) != MP_OKAY) {
248
              goto ERR;
249
250
           if ((res = mp_lshd(&w4, 4*B)) != MP_OKAY) {
251
              goto ERR;
252
253
           if ((res = mp_add(&w0, &w1, c)) != MP_OKAY) \{
254
255
              goto ERR;
256
           if ((res = mp_add(&w2, &w3, &tmp1)) != MP_OKAY) {
257
258
              goto ERR;
259
```

```
260
           if ((res = mp_add(&w4, &tmp1, &tmp1)) != MP_OKAY) {
261
              goto ERR;
262
263
           if ((res = mp_add(&tmp1, c, c)) != MP_OKAY) {
              goto ERR;
264
265
266
267
      ERR:
268
           mp_clear_multi(&w0, &w1, &w2, &w3, &w4,
269
                           &a0, &a1, &a2, &b0, &b1,
270
                           &b2, &tmp1, &tmp2, NULL);
271
           return res;
272
      }
273
```

- Comments to be added during editing phase.

5.2.6 Signed Multiplication

Now that algorithms to handle multiplications of every useful dimensions have been developed, a rather simple finishing touch is required. So far all of the multiplication algorithms have been unsigned multiplications which leaves only a signed multiplication algorithm to be established.

```
Algorithm mp_mul.
Input. mp_int a and mp_int b
Output. c \leftarrow a \cdot b
1. If a.sign = b.sign then
  1.1 \ sign = MP\_ZPOS
2. else
  2.1 \ sign = MP\_ZNEG
3. If min(a.used, b.used) \ge TOOM\_MUL\_CUTOFF then
  3.1 \ c \leftarrow a \cdot b  using algorithm mp_toom_mul
4. else if min(a.used, b.used) \geq KARATSUBA\_MUL\_CUTOFF then
  4.1 \ c \leftarrow a \cdot b \text{ using algorithm mp\_karatsuba\_mul}
5. else
  5.1 \ digs \leftarrow a.used + b.used + 1
  5.2 If digs < MP\_ARRAY and min(a.used, b.used) < \delta then
    5.2.1 c \leftarrow a \cdot b \pmod{\beta^{digs}} using algorithm fast_s_mp_mul_digs.
  5.3 else
    5.3.1 c \leftarrow a \cdot b \pmod{\beta^{digs}} using algorithm s_mp_mul_digs.
6. c.sign \leftarrow sign
7. Return the result of the unsigned multiplication performed.
```

Figure 5.10: Algorithm mp_mul

Algorithm mp_mul. This algorithm performs the signed multiplication of two inputs. It will make use of any of the three unsigned multiplication algorithms available when the input is of appropriate size. The sign of the result is not set until the end of the algorithm since algorithm s_mp_mul_digs will clear it.

```
File: bn_mp_mul.c
016
017
      /* high level multiplication (handles sign) */
018
      int mp_mul (mp_int * a, mp_int * b, mp_int * c)
019
020
        int
                res, neg;
021
        neg = (a->sign == b->sign) ? MP_ZPOS : MP_NEG;
022
023
        /* use Toom-Cook? */
        if (MIN (a->used, b->used) >= TOOM_MUL_CUTOFF) {
024
025
          res = mp_toom_mul(a, b, c);
        /* use Karatsuba? */
026
```

5.3. SQUARING

```
027
        } else if (MIN (a->used, b->used) >= KARATSUBA_MUL_CUTOFF) {
028
          res = mp_karatsuba_mul (a, b, c);
029
        } else {
030
          /* can we use the fast multiplier?
031
032
           * The fast multiplier can be used if the output will
033
           * have less than MP_WARRAY digits and the number of
034
           * digits won't affect carry propagation
035
           */
036
                  digs = a->used + b->used + 1;
          int.
037
038
          if ((digs < MP_WARRAY) &&
039
              MIN(a->used, b->used) <=
              (1 << ((CHAR_BIT * sizeof (mp_word)) - (2 * DIGIT_BIT)))) {
040
041
            res = fast_s_mp_mul_digs (a, b, c, digs);
042
          } else {
043
            res = s_mp_mul (a, b, c);
044
045
046
        c->sign = neg;
047
        return res;
048
```

The implementation is rather simplistic and is not particularly noteworthy. Line 23 computes the sign of the result using the "?" operator from the C programming language. Line 40 computes δ using the fact that 1 << k is equal to 2^k .

5.3 Squaring

Squaring is a special case of multiplication where both multiplicands are equal. At first it may seem like there is no significant optimization available but in fact there is. Consider the multiplication of 576 against 241. In total there will be nine single precision multiplications performed which are $1 \cdot 6$, $1 \cdot 7$, $1 \cdot 5$, $4 \cdot 6$, $4 \cdot 7$, $4 \cdot 5$, $2 \cdot 6$, $2 \cdot 7$ and $2 \cdot 5$. Now consider the multiplication of 123 against 123. The nine products are $3 \cdot 3$, $3 \cdot 2$, $3 \cdot 1$, $2 \cdot 3$, $2 \cdot 2$, $2 \cdot 1$, $1 \cdot 3$, $1 \cdot 2$ and $1 \cdot 1$. On closer inspection some of the products are equivalent. For example, $3 \cdot 2 = 2 \cdot 3$ and $3 \cdot 1 = 1 \cdot 3$.

For any n-digit input, there are $\frac{(n^2+n)}{2}$ possible unique single precision multiplications required compared to the n^2 required for multiplication. The following

diagram gives an example of the operations required.

Figure 5.11: Squaring Optimization Diagram

Starting from zero and numbering the columns from right to left a very simple pattern becomes obvious. For the purposes of this discussion let x represent the number being squared. The first observation is that in row k the 2k'th column of the product has a $(x_k)^2$ term in it.

The second observation is that every column j in row k where $j \neq 2k$ is part of a double product. Every non-square term of a column will appear twice hence the name "double product". Every odd column is made up entirely of double products. In fact every column is made up of double products and at most one square (see the exercise section).

The third and final observation is that for row k the first unique non-square term, that is, one that hasn't already appeared in an earlier row, occurs at column 2k + 1. For example, on row 1 of the previous squaring, column one is part of the double product with column one from row zero. Column two of row one is a square and column three is the first unique column.

5.3.1 The Baseline Squaring Algorithm

The baseline squaring algorithm is meant to be a catch-all squaring algorithm. It will handle any of the input sizes that the faster routines will not handle.

```
Algorithm s_mp_sqr.
Input. mp_int a
Output. b \leftarrow a^2
1. Init a temporary mp_int of at least 2 \cdot a.used + 1 digits. (mp_init_size)
2. If step 1 failed return(MP_MEM)
3. t.used \leftarrow 2 \cdot a.used + 1
4. For ix from 0 to a.used - 1 do
   Calculate the square.
  4.1 \ \hat{r} \leftarrow t_{2ix} + (a_{ix})^2
  4.2 \ t_{2ix} \leftarrow \hat{r} \ (\text{mod } \beta)
   Calculate the double products after the square.
  4.3 \ u \leftarrow |\hat{r}/\beta|
  4.4 For iy from ix + 1 to a.used - 1 do
      4.4.1 \ \hat{r} \leftarrow 2 \cdot a_{ix} a_{iy} + t_{ix+iy} + u
      4.4.2 \ t_{ix+iy} \leftarrow \hat{r} \pmod{\beta}
      4.4.3~u \leftarrow |\hat{r}/\beta|
  Set the last carry.
   4.5 \text{ While } u > 0 \text{ do}
      4.5.1 iy \leftarrow iy + 1
      4.5.2 \ \hat{r} \leftarrow t_{ix+iy} + u
      4.5.3 \ t_{ix+iy} \leftarrow \hat{r} \pmod{\beta}
      4.5.4~u \leftarrow \lfloor \hat{r}/\beta \rfloor
5. Clamp excess digits of t. (mp\_clamp)
6. Exchange b and t.
7. Clear t (mp\_clear)
8. Return(MP\_OKAY)
```

Figure 5.12: Algorithm s_mp_sqr

Algorithm s_mp_sqr. This algorithm computes the square of an input using the three observations on squaring. It is based fairly faithfully on algorithm 14.16 of HAC [2, pp.596-597]. Similar to algorithm s_mp_mul_digs, a temporary mp_int is allocated to hold the result of the squaring. This allows the destination mp_int to be the same as the source mp_int.

The outer loop of this algorithm begins on step 4. It is best to think of the outer loop as walking down the rows of the partial results, while the inner loop computes the columns of the partial result. Step 4.1 and 4.2 compute the square term for each row, and step 4.3 and 4.4 propagate the carry and compute the double products.

The requirement that a mp_word be able to represent the range $0 \le x < 2\beta^2$ arises from this very algorithm. The product $a_{ix}a_{iy}$ will lie in the range $0 \le x \le \beta^2 - 2\beta + 1$ which is obviously less than β^2 meaning that when it is multiplied by two, it can be properly represented by a mp_word.

Similar to algorithm s_mp_mul_digs, after every pass of the inner loop, the destination is correctly set to the sum of all of the partial results calculated so far. This involves expensive carry propagation which will be eliminated in the next algorithm.

```
File: bn_s_mp_sqr.c
016
017
      /* low level squaring, b = a*a, HAC pp.596-597, Algorithm 14.16 */
018
      int
019
      s_mp_sqr (mp_int * a, mp_int * b)
020
021
        mp_int t;
022
        int
               res, ix, iy, pa;
023
        mp_word r;
024
        mp_digit u, tmpx, *tmpt;
025
026
        pa = a->used;
027
        if ((res = mp_init_size (&t, 2*pa + 1)) != MP_OKAY) {
028
          return res;
029
030
        /* default used is maximum possible size */
031
        t.used = 2*pa + 1;
032
033
034
        for (ix = 0; ix < pa; ix++) {
035
          /* first calculate the digit at 2*ix */
          /* calculate double precision result */
036
          r = ((mp\_word) t.dp[2*ix]) +
037
038
              ((mp_word)a->dp[ix])*((mp_word)a->dp[ix]);
039
040
          /* store lower part in result */
          t.dp[ix+ix] = (mp_digit) (r & ((mp_word) MP_MASK));
041
042
043
          /* get the carry */
                      = (mp_digit)(r >> ((mp_word) DIGIT_BIT));
044
045
          /* left hand side of A[ix] * A[iy] */
046
047
          tmpx
                      = a->dp[ix];
```

5.3. *SQUARING* 125

```
048
049
          /* alias for where to store the results */
050
                      = t.dp + (2*ix + 1);
          tmpt
051
052
          for (iy = ix + 1; iy < pa; iy++) \{
053
            /* first calculate the product */
054
                    = ((mp_word)tmpx) * ((mp_word)a->dp[iy]);
055
056
            /* now calculate the double precision result, note we use
057
             * addition instead of *2 since it's easier to optimize
058
             */
                    = ((mp_word) *tmpt) + r + r + ((mp_word) u);
059
            r
060
            /* store lower part */
061
062
            *tmpt++ = (mp_digit) (r & ((mp_word) MP_MASK));
063
064
            /* get carry */
065
                    = (mp_digit)(r >> ((mp_word) DIGIT_BIT));
066
067
          /* propagate upwards */
068
          while (u != ((mp_digit) 0)) {
069
                    = ((mp_word) *tmpt) + ((mp_word) u);
            *tmpt++ = (mp_digit) (r & ((mp_word) MP_MASK));
070
                    = (mp_digit)(r >> ((mp_word) DIGIT_BIT));
071
072
          }
        }
073
074
075
        mp_clamp (&t);
076
        mp_exch (&t, b);
077
        mp_clear (&t);
078
        return MP_OKAY;
079
```

Inside the outer loop (see line 34) the square term is calculated on line 37. Line 44 extracts the carry from the square term. Aliases for a_{ix} and t_{ix+iy} are initialized on lines 47 and 50 respectively. The doubling is performed using two additions (see line 59) since it is usually faster than shifting, if not at least as fast.

5.3.2 Faster Squaring by the "Comba" Method

A major drawback to the baseline method is the requirement for single precision shifting inside the $O(n^2)$ nested loop. Squaring has an additional drawback that it must double the product inside the inner loop as well. As for multiplication, the Comba technique can be used to eliminate these performance hazards.

The first obvious solution is to make an array of mp_words which will hold all of the columns. This will indeed eliminate all of the carry propagation operations from the inner loop. However, the inner product must still be doubled $O(n^2)$ times. The solution stems from the simple fact that 2a + 2b + 2c = 2(a + b + c). That is the sum of all of the double products is equal to double the sum of all the products. For example, ab + ba + ac + ca = 2ab + 2ac = 2(ab + ac).

However, we cannot simply double all of the columns, since the squares appear only once per row. The most practical solution is to have two mp_word arrays. One array will hold the squares and the other array will hold the double products. With both arrays the doubling and carry propagation can be moved to a O(n) work level outside the $O(n^2)$ level.

127

```
Algorithm fast_s_mp_sqr.
Input. mp_int a
Output. b \leftarrow a^2
Place two arrays of MP_WARRAY mp_words named \hat{W} and \hat{X} on the stack.
1. If b.alloc < 2a.used + 1 then grow b to 2a.used + 1 digits. (mp\_grow).
2. If step 1 failed return (MP\_MEM).
3. for ix from 0 to 2a.used + 1 do
  3.1 \ \hat{W}_{ix} \leftarrow 0
  3.2 \ \hat{X}_{ix} \leftarrow 0
4. for ix from 0 to a.used - 1 do
  Compute the square.
  4.1 \ \hat{X}_{ix+ix} \leftarrow (a_{ix})^2
  Compute the double products.
  4.2 for iy from ix + 1 to a.used - 1 do
     4.2.1 \ \hat{W}_{ix+iy} \leftarrow \hat{W}_{ix+iy} + a_{ix}a_{iy}
5. oldused \leftarrow b.used
6. b.used \leftarrow 2a.used + 1
Double the products and propagate the carries simultaneously.
7. \hat{W}_0 \leftarrow 2\hat{W}_0 + \hat{X}_0
8. for ix from 1 to 2a.used do
  8.1 \ \hat{W}_{ix} \leftarrow 2\hat{W}_{ix} + \hat{X}_{ix}
  8.2 \ \hat{W}_{ix} \leftarrow \hat{W}_{ix} + \lfloor \hat{W}_{ix-1}/\beta \rfloor
  8.3 \ b_{ix-1} \leftarrow W_{ix-1} \pmod{\beta}
9. b_{2a.used} \leftarrow \hat{W}_{2a.used} \pmod{\beta}
10. if 2a.used + 1 < oldused then do
   10.1 for ix from 2a.used + 1 to oldused do
     10.1.1 \ b_{ix} \leftarrow 0
11. Clamp excess digits from b. (mp\_clamp)
12. Return(MP_{-}OKAY).
```

Figure 5.13: Algorithm fast_s_mp_sqr

Algorithm fast_s_mp_sqr. This algorithm computes the square of an input using the Comba technique. It is designed to be a replacement for algorithm s_mp_sqr when the number of input digits is less than **MP_WARRAY** and less than $\frac{\delta}{2}$.

This routine requires two arrays of mp_words to be placed on the stack. The

first array \hat{W} will hold the double products and the second array \hat{X} will hold the squares. Though only at most $\frac{MP_-WARRAY}{2}$ words of \hat{X} are used, it has proven faster on most processors to simply make it a full size array.

The loop on step 3 will zero the two arrays to prepare them for the squaring step. Step 4.1 computes the squares of the product. Note how it simply assigns the value into the \hat{X} array. The nested loop on step 4.2 computes the doubles of the products. This loop computes the sum of the products for each column. They are not doubled until later.

After the squaring loop, the products stored in \hat{W} musted be doubled and the carries propagated forwards. It makes sense to do both operations at the same time. The expression $\hat{W}_{ix} \leftarrow 2\hat{W}_{ix} + \hat{X}_{ix}$ computes the sum of the double product and the squares in place.

```
File: bn_fast_s_mp_sqr.c
016
      /* fast squaring
017
018
019
       * This is the comba method where the columns of the product
       * are computed first then the carries are computed. This
020
021
       * has the effect of making a very simple inner loop that
022
       * is executed the most
023
024
       * W2 represents the outer products and W the inner.
025
026
       * A further optimizations is made because the inner
       * products are of the form "A * B * 2". The *2 part does
027
028
       * not need to be computed until the end which is good
029
       * because 64-bit shifts are slow!
030
031
       * Based on Algorithm 14.16 on pp.597 of HAC.
032
       */
033
034
035
      fast_s_mp_sqr (mp_int * a, mp_int * b)
036
037
                olduse, newused, res, ix, pa;
        mp_word W2[MP_WARRAY], W[MP_WARRAY];
038
039
040
        /* calculate size of product and allocate as required */
041
        pa = a->used;
042
        newused = pa + pa + 1;
043
        if (b->alloc < newused) {
```

5.3. *SQUARING* 129

```
if ((res = mp_grow (b, newused)) != MP_OKAY) {
044
045
            return res;
046
047
        }
048
049
        /* zero temp buffer (columns)
050
         * Note that there are two buffers. Since squaring requires
051
         * a outer and inner product and the inner product requires
052
         * computing a product and doubling it (a relatively expensive
         * op to perform n**2 times if you don't have to) the inner and
053
054
         * outer products are computed in different buffers. This way
055
         * the inner product can be doubled using n doublings instead of
056
         * n**2
057
058
        memset (W, 0, newused * sizeof (mp_word));
059
        memset (W2, 0, newused * sizeof (mp_word));
060
061
        /* This computes the inner product. To simplify the inner N**2 loop
         * the multiplication by two is done afterwards in the N loop.
062
063
        for (ix = 0; ix < pa; ix++) \{
064
065
          /* compute the outer product
066
067
           * Note that every outer product is computed
068
           * for a particular column only once which means that
069
           * there is no need todo a double precision addition
070
           * into the W2[] array.
071
072
          W2[ix + ix] = ((mp_word)a->dp[ix]) * ((mp_word)a->dp[ix]);
073
074
075
            register mp_digit tmpx, *tmpy;
076
            register mp_word *_W;
077
            register int iy;
078
079
            /* copy of left side */
080
            tmpx = a->dp[ix];
081
082
            /* alias for right side */
083
            tmpy = a->dp + (ix + 1);
084
085
            /* the column to store the result in */
```

```
_{W} = W + (ix + ix + 1);
086
087
088
            /* inner products */
            for (iy = ix + 1; iy < pa; iy++) {
089
090
                *_W++ += ((mp_word)tmpx) * ((mp_word)*tmpy++);
091
          }
092
        }
093
094
095
        /* setup dest */
096
        olduse = b->used;
097
        b->used = newused;
098
099
        /* now compute digits
100
101
         * We have to double the inner product sums, add in the
102
         * outer product sums, propagate carries and convert
103
         * to single precision.
104
         */
105
106
          register mp_digit *tmpb;
107
          /* double first value, since the inner products are
108
109
           * half of what they should be
           */
110
          W[0] += W[0] + W2[0];
111
112
113
          tmpb = b->dp;
114
          for (ix = 1; ix < newused; ix++) \{
115
            /* double/add next digit */
            W[ix] += W[ix] + W2[ix];
116
117
118
            /* propagate carry forwards [from the previous digit] */
119
            W[ix] = W[ix] + (W[ix - 1] >> ((mp_word) DIGIT_BIT));
120
121
            /* store the current digit now that the carry isn't
122
             * needed
123
             */
            *tmpb++ = (mp_digit) (W[ix - 1] & ((mp_word) MP_MASK));
124
125
          /* set the last value. Note even if the carry is zero
126
127
           * this is required since the next step will not zero
```

5.3. SQUARING

```
* it if b originally had a value at b->dp[2*a.used]
128
129
          *tmpb++ = (mp_digit) (W[(newused) - 1] & ((mp_word) MP_MASK));
130
131
132
          /* clear high digits of b if there were any originally */
133
          for (; ix < olduse; ix++) {</pre>
            *tmpb++ = 0;
134
135
        }
136
137
138
        mp_clamp (b);
139
        return MP_OKAY;
140
```

- Write something deep and insightful later, Tom.

5.3.3 Polynomial Basis Squaring

The same algorithm that performs optimal polynomial basis multiplication can be used to perform polynomial basis squaring. The minor exception is that $\zeta_y = f(y)g(y)$ is actually equivalent to $\zeta_y = f(y)^2$ since f(y) = g(y). Instead of performing 2n+1 multiplications to find the ζ relations, squaring operations are performed instead.

5.3.4 Karatsuba Squaring

Let f(x) = ax + b represent the polynomial basis representation of a number to square. Let $h(x) = (f(x))^2$ represent the square of the polynomial. The Karatsuba equation can be modified to square a number with the following equation.

$$h(x) = a^2 x^2 + (a^2 + b^2 - (a - b)^2) x + b^2$$
(5.7)

Upon closer inspection this equation only requires the calculation of three half-sized squares: a^2 , b^2 and $(a-b)^2$. As in Karatsuba multiplication, this algorithm can be applied recursively on the input and will achieve an asymptotic running time of $O(n^{lg(3)})$.

You might ask yourself, if the asymptotic time of Karatsuba squaring and multiplication is the same, why not simply use the multiplication algorithm instead? The answer to this arises from the cutoff point for squaring. As in multiplication there exists a cutoff point, at which the time required for a Comba

based squaring and a Karatsuba based squaring meet. Due to the overhead inherent in the Karatsuba method, the cutoff point is fairly high. For example, on an AMD Athlon XP processor with $\beta=2^{28}$, the cutoff point is around 127 digits.

Consider squaring a 200 digit number with this technique. It will be split into two 100 digit halves which are subsequently squared. The 100 digit halves will not be squared using Karatsuba, but instead using the faster Comba based squaring algorithm. If Karatsuba multiplication were used instead, the 100 digit numbers would be squared with a slower Comba based multiplication.

5.3. SQUARING

133

```
Algorithm mp_karatsuba_sqr.
Input. mp_int a
Output. b \leftarrow a^2
1. Initialize the following temporary mp_ints: x0, x1, t1, t2, x0x0 and x1x1.
2. If any of the initializations on step 1 failed return (MP\_MEM).
Split the input. e.g. a = x1\beta^B + x0
3. B \leftarrow |a.used/2|
4. x0 \leftarrow a \pmod{\beta^B} \pmod{2d}
5. x1 \leftarrow \lfloor a/\beta^B \rfloor \ (mp\_lshd)
Calculate the three squares.
6. x0x0 \leftarrow x0^2 \ (mp\_sqr)
7. x1x1 \leftarrow x1^2
8. t1 \leftarrow x1 - x0 \ (mp\_sub)
9. t1 \leftarrow t1^2
Compute the middle term.
10. t2 \leftarrow x0x0 + x1x1 \ (s\_mp\_add)
11. t1 \leftarrow t2 - t1
Compute final product.
12. t1 \leftarrow t1\beta^B \ (mp\_lshd)
13. x1x1 \leftarrow x1x1\beta^{2B}
14. t1 \leftarrow t1 + x0x0
15. b \leftarrow t1 + x1x1
16. Return(MP\_OKAY).
```

Figure 5.14: Algorithm mp_karatsuba_sqr

Algorithm mp_karatsuba_sqr. This algorithm computes the square of an input a using the Karatsuba technique. This algorithm is very similar to the Karatsuba based multiplication algorithm with the exception that the three half-size multiplications have been replaced with three half-size squarings.

The radix point for squaring is simply placed exactly in the middle of the digits when the input has an odd number of digits, otherwise it is placed just below the middle. Step 3, 4 and 5 compute the two halves required using B as the radix point. The first two squares in steps 6 and 7 are rather straightforward while the last square is of a more compact form.

By expanding $(x1-x0)^2$, the $x1^2$ and $x0^2$ terms in the middle disappear, that is $x1^2+x0^2-(x1-x0)^2=2\cdot x0\cdot x1$. Now if 5n single precision additions and a squaring of n-digits is faster than multiplying two n-digit numbers and doubling then this method is faster. Assuming no further recursions occur, the difference can be estimated with the following inequality.

Let p represent the cost of a single precision addition and q the cost of a single precision multiplication both in terms of time⁵.

$$5pn + \frac{q(n^2 + n)}{2} \le pn + qn^2 \tag{5.8}$$

For example, on an AMD Athlon XP processor $p = \frac{1}{3}$ and q = 6. This implies that the following inequality should hold.

This results in a cutoff point around n=2. As a consequence it is actually faster to compute the middle term the "long way" on processors where multiplication is substantially slower⁶ than simpler operations such as addition.

```
File: bn_mp_karatsuba_sqr.c
```

```
016
017
      /* Karatsuba squaring, computes b = a*a using three
018
       * half size squarings
019
020
       * See comments of mp_karatsuba_mul for details.
       * is essentially the same algorithm but merely
021
022
       * tuned to perform recursive squarings.
023
024
      int
025
      mp_karatsuba_sqr (mp_int * a, mp_int * b)
026
027
        mp_int x0, x1, t1, t2, x0x0, x1x1;
028
                B, err;
029
030
        err = MP_MEM;
```

⁵Or machine clock cycles.

⁶On the Athlon there is a 1:17 ratio between clock cycles for addition and multiplication. On the Intel P4 processor this ratio is 1:29 making this method even more beneficial. The only common exception is the ARMv4 processor which has a ratio of 1:7.

5.3. SQUARING 135

```
031
032
        /* min # of digits */
033
        B = a->used;
034
035
        /* now divide in two */
036
        B = B / 2;
037
038
        /* init copy all the temps */
039
        if (mp_init_size (&x0, B) != MP_OKAY)
040
          goto ERR;
041
        if (mp_init_size (&x1, a->used - B) != MP_OKAY)
042
          goto X0;
043
044
        /* init temps */
045
        if (mp_init_size (&t1, a->used * 2) != MP_OKAY)
046
          goto X1;
047
        if (mp_init_size (&t2, a->used * 2) != MP_OKAY)
048
          goto T1;
049
        if (mp_init_size (&x0x0, B * 2) != MP_OKAY)
050
          goto T2;
051
        if (mp_init_size (\&x1x1, (a-)used - B) * 2) != MP_OKAY)
052
          goto XOXO;
053
054
055
          register int x;
056
          register mp_digit *dst, *src;
057
058
          src = a->dp;
059
060
          /* now shift the digits */
061
          dst = x0.dp;
062
          for (x = 0; x < B; x++) {
063
            *dst++ = *src++;
064
065
066
          dst = x1.dp;
067
          for (x = B; x < a->used; x++) {
068
            *dst++ = *src++;
069
070
        }
071
072
        x0.used = B;
```

```
073
        x1.used = a->used - B;
074
075
        mp_clamp (&x0);
076
077
        /* now calc the products x0*x0 and x1*x1 */
078
        if (mp_sqr (&x0, &x0x0) != MP_OKAY)
079
          goto X1X1;
                               /* x0x0 = x0*x0 */
        if (mp_sqr (&x1, &x1x1) != MP_OKAY)
080
081
          goto X1X1;
                               /* x1x1 = x1*x1 */
082
083
        /* now calc (x1-x0)**2 */
084
        if (mp_sub (&x1, &x0, &t1) != MP_OKAY)
085
          goto X1X1;
                               /* t1 = x1 - x0 */
086
        if (mp_sqr (&t1, &t1) != MP_OKAY)
087
          goto X1X1;
                               /* t1 = (x1 - x0) * (x1 - x0) */
088
089
        /* add x0y0 */
090
        if (s_mp_add (&x0x0, &x1x1, &t2) != MP_OKAY)
          goto X1X1;
091
                               /* t2 = x0x0 + x1x1 */
        if (mp_sub (&t2, &t1, &t1) != MP_OKAY)
092
093
                               /* t1 = x0x0 + x1x1 - (x1-x0)*(x1-x0) */
          goto X1X1;
094
        /* shift by B */
095
096
        if (mp_lshd (&t1, B) != MP_OKAY)
097
          goto X1X1;
                               /* t1 = (x0x0 + x1x1 - (x1-x0)*(x1-x0)) << B */
098
        if (mp_1shd (\&x1x1, B * 2) != MP_0KAY)
099
          goto X1X1;
                               /* x1x1 = x1x1 << 2*B */
100
101
        if (mp_add (&x0x0, &t1, &t1) != MP_OKAY)
102
          goto X1X1;
                                /* t1 = x0x0 + t1 */
103
        if (mp_add (&t1, &x1x1, b) != MP_OKAY)
104
          goto X1X1;
                               /* t1 = x0x0 + t1 + x1x1 */
105
106
        err = MP_OKAY;
107
108
      X1X1:mp_clear (&x1x1);
      X0X0:mp_clear (&x0x0);
109
110
      T2:mp_clear (&t2);
      T1:mp_clear (&t1);
111
      X1:mp_clear (&x1);
112
113
      X0:mp_clear (&x0);
114
      ERR:
```

```
115    return err;
116  }
```

This implementation is largely based on the implementation of algorithm mp_karatsuba_mul. It uses the same inline style to copy and shift the input into the two halves. The loop from line 54 to line 70 has been modified since only one input exists. The **used** count of both x0 and x1 is fixed up and x0 is clamped before the calculations begin. At this point x1 and x0 are valid equivalents to the respective halves as if mp_rshd and mp_mod_2d had been used.

By inlining the copy and shift operations the cutoff point for Karatsuba multiplication can be lowered. On the Athlon the cutoff point is exactly at the point where Comba squaring can no longer be used (128 digits). On slower processors such as the Intel P4 it is actually below the Comba limit (at 110 digits).

This routine uses the same error trap coding style as mp_karatsuba_sqr. As the temporary variables are initialized errors are redirected to the error trap higher up. If the algorithm completes without error the error code is set to MP_OKAY and mp_clears are executed normally.

Last paragraph sucks. re-write! - Tom

5.3.5 Toom-Cook Squaring

The Toom-Cook squaring algorithm mp_toom_sqr is heavily based on the algorithm mp_toom_mul with the exception that squarings are used instead of multiplication to find the five relations.. The reader is encouraged to read the description of the latter algorithm and try to derive their own Toom-Cook squaring algorithm.

5.3.6 High Level Squaring

```
Algorithm mp_sqr.

Input. mp_int a
Output. b \leftarrow a^2

1. If a.used \geq TOOM\_SQR\_CUTOFF then
1.1 \ b \leftarrow a^2 using algorithm mp_toom_sqr

2. else if a.used \geq KARATSUBA\_SQR\_CUTOFF then
2.1 \ b \leftarrow a^2 using algorithm mp_karatsuba_sqr

3. else
3.1 \ digs \leftarrow a.used + b.used + 1
3.2 \ lf \ digs < MP\_ARRAY and a.used \leq \delta then
3.2.1 \ b \leftarrow a^2 using algorithm fast_s_mp_sqr.

3.3 else
3.3.1 \ b \leftarrow a^2 using algorithm s_mp_sqr.

4. b.sign \leftarrow MP\_ZPOS

5. Return the result of the unsigned squaring performed.
```

Figure 5.15: Algorithm mp_sqr

Algorithm mp_sqr. This algorithm computes the square of the input using one of four different algorithms. If the input is very large and has at least TOOM_SQR_CUTOFF or KARATSUBA_SQR_CUTOFF digits then either the Toom-Cook or the Karatsuba Squaring algorithm is used. If neither of the polynomial basis algorithms should be used then either the Comba or baseline algorithm is used.

```
File: bn_mp_sqr.c
016
017
      /* computes b = a*a */
018
      mp_sqr (mp_int * a, mp_int * b)
019
020
021
        int
                res;
022
        /* use Toom-Cook? */
023
        if (a->used >= TOOM_SQR_CUTOFF) {
024
025
          res = mp_toom_sqr(a, b);
026
        /* Karatsuba? */
        } else if (a->used >= KARATSUBA_SQR_CUTOFF) {
027
          res = mp_karatsuba_sqr (a, b);
028
029
        } else {
```

5.3. SQUARING

139

```
030
          /* can we use the fast comba multiplier? */
031
          if ((a->used * 2 + 1) < MP_WARRAY &&
032
               a->used <
               (1 << (sizeof(mp_word) * CHAR_BIT - 2*DIGIT_BIT - 1))) {
033
034
            res = fast_s_mp_sqr (a, b);
035
          } else {
036
            res = s_mp_sqr (a, b);
037
038
        b->sign = MP_ZPOS;
039
040
        return res;
041
      }
```

Exercises

- [3] Devise an efficient algorithm for selection of the radix point to handle inputs that have different number of digits in Karatsuba multiplication.
- [3] In section 5.3 the fact that every column of a squaring is made up of double products and at most one square is stated. Prove this statement.
- [2] In the Comba squaring algorithm half of the \hat{X} variables are not used. Revise algorithm fast_s_mp_sqr to shrink the \hat{X} array.
- [3] Prove the equation for Karatsuba squaring.
- [1] Prove that Karatsuba squaring requires $O(n^{lg(3)})$ time.
- [2] Determine the minimal ratio between addition and multiplication clock cycles required for equation 6.7 to be true.

Chapter 6

Modular Reduction

6.1 Basics of Modular Reduction

Modular reduction is an operation that arises quite often within public key cryptography algorithms and various number theoretic algorithms, such as factoring. Modular reduction algorithms are the third class of algorithms of the "multipliers" set. A number a is said to be reduced modulo another number b by finding the remainder of the division a/b. Full integer division with remainder is a topic to be covered in 8.1.

Modular reduction is equivalent to solving for r in the following equation. a = bq + r where $q = \lfloor a/b \rfloor$. The result r is said to be "congruent to a modulo b" which is also written as $r \equiv a \pmod{b}$. In other vernacular r is known as the "modular residue" which leads to "quadratic residue" and other forms of residues.

Modular reductions are normally used to create either finite groups, rings or fields. The most common usage for performance driven modular reductions is in modular exponentiation algorithms. That is to compute $d=a^b\pmod{c}$ as fast as possible. This operation is used in the RSA and Diffie-Hellman public key algorithms, for example. Modular multiplication and squaring also appears as a fundamental operation in Elliptic Curve cryptographic algorithms. As will be discussed in the subsequent chapter there exist fast algorithms for computing modular exponentiations without having to perform (in this example) b-1 multiplications. These algorithms will produce partial results in the

¹That's fancy talk for $b \equiv a^2 \pmod{p}$.

range $0 \le x < c^2$ which can be taken advantage of to create several efficient algorithms. They have also been used to create redundancy check algorithms known as CRCs, error correction codes such as Reed-Solomon and solve a variety of number theoretic problems.

6.2 The Barrett Reduction

The Barrett reduction algorithm [7] was inspired by fast division algorithms which multiply by the reciprocal to emulate division. Barretts observation was that the residue c of a modulo b is equal to

$$c = a - b \cdot \lfloor a/b \rfloor \tag{6.1}$$

Since algorithms such as modular exponentiation would be using the same modulus extensively, typical DSP^2 intuition would indicate the next step would be to replace a/b by a multiplication by the reciprocal. However, DSP intuition on its own will not work as these numbers are considerably larger than the precision of common DSP floating point data types. It would take another common optimization to optimize the algorithm.

6.2.1 Fixed Point Arithmetic

The trick used to optimize the above equation is based on a technique of emulating floating point data types with fixed precision integers. Fixed point arithmetic would become very popular as it greatly optimize the "3d-shooter" genre of games in the mid 1990s when floating point units were fairly slow if not unavailable. The idea behind fixed point arithmetic is to take a normal k-bit integer data type and break it into p-bit integer and a q-bit fraction part (where p + q = k).

In this system a k-bit integer n would actually represent $n/2^q$. For example, with q=4 the integer n=37 would actually represent the value 2.3125. To multiply two fixed point numbers the integers are multiplied using traditional arithmetic and subsequently normalized by moving the implied decimal point back to where it should be. For example, with q=4 to multiply the integers 9 and 5 they must be converted to fixed point first by multiplying by 2^q . Let $a=9(2^q)$ represent the fixed point representation of 9 and $b=5(2^q)$ represent

²It is worth noting that Barrett's paper targeted the DSP56K processor.

the fixed point representation of 5. The product ab is equal to $45(2^{2q})$ which when normalized by dividing by 2^q produces $45(2^q)$.

This technique became popular since a normal integer multiplication and logical shift right are the only required operations to perform a multiplication of two fixed point numbers. Using fixed point arithmetic, division can be easily approximated by multiplying by the reciprocal. If 2^q is equivalent to one than $2^q/b$ is equivalent to the fixed point approximation of 1/b using real arithmetic. Using this fact dividing an integer a by another integer b can be achieved with the following expression.

$$|a/b| \sim |(a \cdot |2^q/b|)/2^q|$$
 (6.2)

The precision of the division is proportional to the value of q. If the divisor b is used frequently as is the case with modular exponentiation pre-computing $2^q/b$ will allow a division to be performed with a multiplication and a right shift. Both operations are considerably faster than division on most processors.

Consider dividing 19 by 5. The correct result is $\lfloor 19/5 \rfloor = 3$. With q = 3 the reciprocal is $\lfloor 2^q/5 \rfloor = 1$ which leads to a product of 19 which when divided by 2^q produces 2. However, with q = 4 the reciprocal is $\lfloor 2^q/5 \rfloor = 3$ and the result of the emulated division is $\lfloor 3 \cdot 19/2^q \rfloor = 3$ which is correct. The value of 2^q must be close to or ideally larger than the dividend. In effect if a is the dividend then q should allow $0 \leq \lfloor a/2^q \rfloor \leq 1$ in order for this approach to work correctly. Plugging this form of divison into the original equation the following modular residue equation arises.

$$c = a - b \cdot \lfloor (a \cdot \lfloor 2^q/b \rfloor)/2^q \rfloor \tag{6.3}$$

Using the notation from [7] the value of $\lfloor 2^q/b \rfloor$ will be represented by the μ symbol. Using the μ variable also helps re-inforce the idea that it is meant to be computed once and re-used.

$$c = a - b \cdot \lfloor (a \cdot \mu)/2^q \rfloor \tag{6.4}$$

Provided that $2^q \ge a$ this algorithm will produce a quotient that is either exactly correct or off by a value of one. In the context of Barrett reduction the value of a is bound by $0 \le a \le (b-1)^2$ meaning that $2^q \ge b^2$ is sufficient to ensure the reciprocal will have enough precision.

Let n represent the number of digits in b. This algorithm requires approximately $2n^2$ single precision multiplications to produce the quotient and another n^2 single precision multiplications to find the residue. In total $3n^2$ single precision multiplications are required to reduce the number.

For example, if b=1179677 and q=41 $(2^q>b^2)$, then the reciprocal μ is equal to $\lfloor 2^q/b\rfloor=1864089$. Consider reducing a=180388626447 modulo b using the above reduction equation. The quotient using the new formula is $\lfloor (a\cdot\mu)/2^q\rfloor=152913$. By subtracting 152913b from a the correct residue $a\equiv 677346\pmod{b}$ is found.

6.2.2 Choosing a Radix Point

Using the fixed point representation a modular reduction can be performed with $3n^2$ single precision multiplications. If that were the best that could be achieved a full division³ might as well be used in its place. The key to optimizing the reduction is to reduce the precision of the initial multiplication that finds the quotient.

Let a represent the number of which the residue is sought. Let b represent the modulus used to find the residue. Let m represent the number of digits in b. For the purposes of this discussion we will assume that the number of digits in a is 2m, which is generally true if two m-digit numbers have been multiplied. Dividing a by b is the same as dividing a 2m digit integer by a m digit integer. Digits below the m-1'th digit of a will contribute at most a value of 1 to the quotient because $\beta^k < b$ for any $0 \le k \le m-1$. Another way to express this is by re-writing a as two parts. If $a' \equiv a \pmod{b^m}$ and a'' = a - a' then $\frac{a}{b} \equiv \frac{a' + a''}{b}$ which is equivalent to $\frac{a'}{b} + \frac{a''}{b}$. Since a' is bound to be less than b the quotient is bound by $0 \le \frac{a'}{b} < 1$.

Since the digits of a' do not contribute much to the quotient the observation is that they might as well be zero. However, if the digits "might as well be zero" they might as well not be there in the first place. Let $q_0 = \lfloor a/\beta^{m-1} \rfloor$ represent the input with the irrelevant digits trimmed. Now the modular reduction is trimmed to the almost equivalent equation

$$c = a - b \cdot \lfloor (q_0 \cdot \mu) / \beta^{m+1} \rfloor \tag{6.5}$$

Note that the original divisor 2^q has been replaced with β^{m+1} where in this case q is a multiple of $lg(\beta)$. Also note that the exponent on the divisor when added to the amount q_0 was shifted by equals 2m. If the optimization had not been performed the divisor would have the exponent 2m so in the end the exponents do "add up". Using the above equation the quotient $\lfloor (q_0 \cdot \mu)/\beta^{m+1} \rfloor$ can be off from the true quotient by at most two. The original fixed point

 $^{^3}$ A division requires approximately $O(2cn^2)$ single precision multiplications for a small value of c. See 8.1 for further details.

quotient can be off by as much as one (provided the radix point is chosen suitably) and now that the lower irrelevent digits have been trimmed the quotient can be off by an additional value of one for a total of at most two. This implies that $0 \le a - b \cdot \lfloor (q_0 \cdot \mu)/\beta^{m+1} \rfloor < 3b$. By first subtracting b times the quotient and then conditionally subtracting b once or twice the residue is found.

The quotient is now found using $(m+1)(m) = m^2 + m$ single precision multiplications and the residue with an additional m^2 single precision multiplications, ignoring the subtractions required. In total $2m^2 + m$ single precision multiplications are required to find the residue. This is considerably faster than the original attempt.

For example, let $\beta=10$ represent the radix of the digits. Let b=9999 represent the modulus which implies m=4. Let a=99929878 represent the value of which the residue is desired. In this case q=8 since $10^7<9999^2$ meaning that $\mu=\lfloor\beta^q/b\rfloor=10001$. With the new observation the multiplicand for the quotient is equal to $q_0=\lfloor a/\beta^{m-1}\rfloor=99929$. The quotient is then $\lfloor (q_0\cdot\mu)/\beta^{m+1}\rfloor=9993$. Subtracting 9993b from a and the correct residue $a\equiv9871\pmod{b}$ is found.

6.2.3 Trimming the Quotient

So far the reduction algorithm has been optimized from $3m^2$ single precision multiplications down to $2m^2+m$ single precision multiplications. As it stands now the algorithm is already fairly fast compared to a full integer division algorithm. However, there is still room for optimization.

After the first multiplication inside the quotient $(q_0 \cdot \mu)$ the value is shifted right by m+1 places effectively nullifying the lower half of the product. It would be nice to be able to remove those digits from the product to effectively cut down the number of single precision multiplications. If the number of digits in the modulus m is far less than β a full product is not required for the algorithm to work properly. In fact the lower m-2 digits will not affect the upper half of the product at all and do not need to be computed.

The value of μ is a m-digit number and q_0 is a m+1 digit number. Using a full multiplier $(m+1)(m)=m^2+m$ single precision multiplications would be required. Using a multiplier that will only produce digits at and above the m-1'th digit reduces the number of single precision multiplications to $\frac{m^2+m}{2}$ single precision multiplications.

6.2.4 Trimming the Residue

After the quotient has been calculated it is used to reduce the input. As previously noted the algorithm is not exact and it can be off by a small multiple of the modulus, that is $0 \le a - b \cdot \lfloor (q_0 \cdot \mu)/\beta^{m+1} \rfloor < 3b$. If b is m digits than the result of reduction equation is a value of at most m+1 digits (provided $3 < \beta$) implying that the upper m-1 digits are implicitly zero.

The next optimization arises from this very fact. Instead of computing $b \cdot \lfloor (q_0 \cdot \mu)/\beta^{m+1} \rfloor$ using a full $O(m^2)$ multiplication algorithm only the lower m+1 digits of the product have to be computed. Similarly the value of a can be reduced modulo β^{m+1} before the multiple of b is subtracted which simplifies the subtraction as well. A multiplication that produces only the lower m+1 digits requires $\frac{m^2+3m-2}{2}$ single precision multiplications.

With both optimizations in place the algorithm is the algorithm Barrett proposed. It requires $m^2 + 2m - 1$ single precision multiplications which is considerably faster than the straightforward $3m^2$ method.

6.2.5 The Barrett Algorithm

```
Algorithm mp_reduce.
Input. mp_int a, mp_int b and \mu = \lfloor \beta^{2m}/b \rfloor, m = \lceil lg_{\beta}(b) \rceil, (0 \le a < b^2, b > 1)
Output. a \pmod{b}
Let m represent the number of digits in b.
1. Make a copy of a and store it in q. (mp\_init\_copy)
2. q \leftarrow \lfloor q/\beta^{m-1} \rfloor \ (mp\_rshd)
Produce the quotient.
3. q \leftarrow q \cdot \mu (note: only produce digits at or above m-1)
4. q \leftarrow \lfloor q/\beta^{m+1} \rfloor
Subtract the multiple of modulus from the input.
5. a \leftarrow a \pmod{\beta^{m+1}} \pmod{2d}
6. q \leftarrow q \cdot b \pmod{\beta^{m+1}} (s_m p_m u l_d i g s)
7. a \leftarrow a - q \ (mp\_sub)
Add \beta^{m+1} if a carry occured.
8. If a < 0 then (mp\_cmp\_d)
  8.1 \ q \leftarrow 1 \ (mp\_set)
  8.2 \ q \leftarrow q \cdot \beta^{m+1} \ (mp\_lshd)
  8.3 \ a \leftarrow a + q
Now subtract the modulus if the residue is too large (e.g. quotient too small).
9. While a \geq b do (mp\_cmp)
  9.1 \ c \leftarrow a - b
10. Clear q.
11. Return(MP\_OKAY)
```

Figure 6.1: Algorithm mp_reduce

Algorithm mp_reduce. This algorithm will reduce the input a modulo b in place using the Barrett algorithm. It is loosely based on algorithm 14.42 of HAC [2, pp. 602] which is based on the paper from Paul Barrett [7]. The algorithm has several restrictions and assumptions which must be adhered to for the algorithm to work.

First the modulus b is assumed to be positive and greater than one. If the modulus were less than or equal to one than subtracting a multiple of it would either accomplish nothing or actually enlarge the input. The input a must be in the range $0 \le a < b^2$ in order for the quotient to have enough precision. If a

is the product of two numbers that were already reduced modulo b, this will not be a problem. Technically the algorithm will still work if $a \ge b^2$ but it will take much longer to finish. The value of μ is passed as an argument to this algorithm and is assumed to be calculated and stored before the algorithm is used.

Recall that the multiplication for the quotient on step 3 must only produce digits at or above the m-1'th position. An algorithm called $s_mp_mul_high_digs$ which has not been presented is used to accomplish this task. The algorithm is based on $s_mp_mul_digs$ except that instead of stopping at a given level of precision it starts at a given level of precision. This optimal algorithm can only be used if the number of digits in b is very much smaller than b.

While it is known that $a \geq b \cdot \lfloor (q_0 \cdot \mu)/\beta^{m+1} \rfloor$ only the lower m+1 digits are being used to compute the residue, so an implied "borrow" from the higher digits might leave a negative result. After the multiple of the modulus has been subtracted from a the residue must be fixed up in case it is negative. The invariant β^{m+1} must be added to the residue to make it positive again.

The while loop at step 9 will subtract b until the residue is less than b. If the algorithm is performed correctly this step is performed at most twice, and on average once. However, if $a \ge b^2$ than it will iterate substantially more times than it should.

```
File: bn_mp_reduce.c
016
      /* reduces x mod m, assumes 0 < x < m**2, mu is
017
018
       * precomputed via mp_reduce_setup.
019
       * From HAC pp.604 Algorithm 14.42
020
       */
021
      mp_reduce (mp_int * x, mp_int * m, mp_int * mu)
022
023
024
        mp_int q;
025
        int.
                res, um = m->used;
026
027
        /* q = x */
028
        if ((res = mp_init_copy (&q, x)) != MP_OKAY) {
029
          return res;
030
        }
031
        /* q1 = x / b**(k-1) */
032
033
        mp_rshd (&q, um - 1);
034
035
        /* according to HAC this optimization is ok */
```

```
036
        if (((unsigned long) um) > (((mp_digit)1) << (DIGIT_BIT - 1))) {</pre>
037
          if ((res = mp_mul (&q, mu, &q)) != MP_OKAY) {
038
            goto CLEANUP;
039
040
        } else {
041
          if ((res = s_mp_mul_high_digs (&q, mu, &q, um - 1)) != MP_OKAY) {
042
            goto CLEANUP;
043
044
        }
045
        /* q3 = q2 / b**(k+1) */
046
047
        mp_rshd (&q, um + 1);
048
049
        /* x = x \mod b**(k+1), quick (no division) */
050
        if ((res = mp_mod_2d (x, DIGIT_BIT * (um + 1), x)) != MP_OKAY) {
051
          goto CLEANUP;
052
053
054
        /* q = q * m \mod b**(k+1), quick (no division) */
055
        if ((res = s_mp_mul_digs (&q, m, &q, um + 1)) != MP_OKAY) {
056
          goto CLEANUP;
057
        }
058
059
        /* x = x - q */
060
        if ((res = mp_sub (x, &q, x)) != MP_OKAY) {
061
          goto CLEANUP;
062
        }
063
064
        /* If x < 0, add b**(k+1) to it */
065
        if (mp\_cmp\_d (x, 0) == MP\_LT) {
066
          mp_set (&q, 1);
067
          if ((res = mp_lshd (&q, um + 1)) != MP_OKAY)
068
            goto CLEANUP;
069
          if ((res = mp\_add (x, &q, x)) != MP\_OKAY)
070
            goto CLEANUP;
071
072
073
        /* Back off if it's too big */
074
        while (mp\_cmp (x, m) != MP\_LT) {
075
          if ((res = s_mp_sub (x, m, x)) != MP_OKAY) {
            goto CLEANUP;
076
077
```

```
078 }
079
080 CLEANUP:
081 mp_clear (&q);
082
083 return res;
084 }
```

The first multiplication that determines the quotient can be performed by only producing the digits from m-1 and up. This essentially halves the number of single precision multiplications required. However, the optimization is only safe if β is much larger than the number of digits in the modulus. In the source code this is evaluated on lines 36 to 44 where algorithm s_mp_mul_high_digs is used when it is safe to do so.

6.2.6 The Barrett Setup Algorithm

In order to use algorithm mp_reduce the value of μ must be calculated in advance. Ideally this value should be computed once and stored for future use so that the Barrett algorithm can be used without delay.

```
Algorithm mp_reduce_setup.
Input. mp_int a (a > 1)
Output. \mu \leftarrow \lfloor \beta^{2m}/a \rfloor

1. \mu \leftarrow 2^{2 \cdot lg(\beta) \cdot m} (mp\_2expt)
2. \mu \leftarrow \lfloor \mu/b \rfloor (mp\_div)
3. Return(MP\_OKAY)
```

Figure 6.2: Algorithm mp_reduce_setup

Algorithm mp_reduce_setup. This algorithm computes the reciprocal μ required for Barrett reduction. First β^{2m} is calculated as $2^{2 \cdot lg(\beta) \cdot m}$ which is equivalent and much faster. The final value is computed by taking the integer quotient of $\lfloor \mu/b \rfloor$.

```
File: bn_mp_reduce_setup.c
016
017    /* pre-calculate the value required for Barrett reduction
018    * For a given modulus "b" it calulates the value required in "a"
019    */
```

```
020
      mp_reduce_setup (mp_int * a, mp_int * b)
021
022
023
        int
                res:
024
        if ((res = mp_2expt (a, b->used * 2 * DIGIT_BIT)) != MP_OKAY) {
025
026
          return res:
027
028
        return mp_div (a, b, a, NULL);
029
      }
```

This simple routine calculates the reciprocal μ required by Barrett reduction. Note the extended usage of algorithm mp_div where the variable which would received the remainder is passed as NULL. As will be discussed in 8.1 the division routine allows both the quotient and the remainder to be passed as NULL meaning to ignore the value.

6.3 The Montgomery Reduction

Montgomery reduction⁴ [8] is by far the most interesting form of reduction in common use. It computes a modular residue which is not actually equal to the residue of the input yet instead equal to a residue times a constant. However, as perplexing as this may sound the algorithm is relatively simple and very efficient.

Throughout this entire section the variable n will represent the modulus used to form the residue. As will be discussed shortly the value of n must be odd. The variable x will represent the quantity of which the residue is sought. Similar to the Barrett algorithm the input is restricted to $0 \le x < n^2$. To begin the description some simple number theory facts must be established.

Fact 1. Adding n to x does not change the residue since in effect it adds one to the quotient $\lfloor x/n \rfloor$. Another way to explain this is that n is (or multiples of n are) congruent to zero modulo n. Adding zero will not change the value of the residue.

Fact 2. If x is even then performing a division by two in \mathbb{Z} is congruent to $x \cdot 2^{-1} \pmod{n}$. Actually this is an application of the fact that if x is evenly divisible by any $k \in \mathbb{Z}$ then division in \mathbb{Z} will be congruent to multiplication by k^{-1} modulo n.

From these two simple facts the following simple algorithm can be derived.

⁴Thanks to Niels Ferguson for his insightful explanation of the algorithm.

```
Algorithm Montgomery Reduction. Input. Integer x, n and k Output. 2^{-k}x \pmod{n}

1. for t from 1 to k do
1.1 If x is odd then
1.1.1 x \leftarrow x + n
1.2 x \leftarrow x/2
2. Return x.
```

Figure 6.3: Algorithm Montgomery Reduction

The algorithm reduces the input one bit at a time using the two congruencies stated previously. Inside the loop n, which is odd, is added to x if x is odd. This forces x to be even which allows the division by two in $\mathbb Z$ to be congruent to a modular division by two. Since x is assumed to be initially much larger than n the addition of n will contribute an insignificant magnitude to x. Let r represent the final result of the Montgomery algorithm. If k > lg(n) and $0 \le x < n^2$ then the final result is limited to $0 \le r < \lfloor x/2^k \rfloor + n$. As a result at most a single subtraction is required to get the residue desired.

Step number (t)	Result (x)
1	x + n = 5812, x/2 = 2906
2	x/2 = 1453
3	x + n = 1710, x/2 = 855
4	x + n = 1112, x/2 = 556
5	x/2 = 278
6	x/2 = 139
7	x + n = 396, x/2 = 198
8	x/2 = 99

Figure 6.4: Example of Montgomery Reduction (I)

Consider the example in figure 6.4 which reduces x=5555 modulo n=257 when k=8. The result of the algorithm r=99 is congruent to the value of $2^{-8} \cdot 5555 \pmod{257}$. When r is multiplied by 2^8 modulo 257 the correct residue $r \equiv 158$ is produced.

Let $k = \lfloor lg(n) \rfloor + 1$ represent the number of bits in n. The current algorithm requires $2k^2$ single precision shifts and k^2 single precision additions. At this rate

the algorithm is most certainly slower than Barrett reduction and not terribly useful. Fortunately there exists an alternative representation of the algorithm.

```
Algorithm Montgomery Reduction (modified I). Input. Integer x, n and k Output. 2^{-k}x (mod n)

1. for t from 0 to k-1 do
1.1 If the t'th bit of x is one then
1.1.1 x \leftarrow x + 2^t n
2. Return x/2^k.
```

Figure 6.5: Algorithm Montgomery Reduction (modified I)

This algorithm is equivalent since $2^t n$ is a multiple of n and the lower k bits of x are zero by step 2. The number of single precision shifts has now been reduced from $2k^2$ to $k^2 + k$ which is only a small improvement.

Step number (t)	Result (x)	Result (x) in Binary
_	5555	1010110110011
1	$x + 2^0 n = 5812$	1011010110100
2	5812	1011010110100
3	$x + 2^2 n = 6840$	1101010111000
4	$x + 2^3 n = 8896$	10001011000000
5	8896	10001011000000
6	8896	10001011000000
7	$x + 2^6 n = 25344$	110001100000000
8	25344	110001100000000
_	$x/2^k = 99$	

Figure 6.6: Example of Montgomery Reduction (II)

Figure 6.6 demonstrates the modified algorithm reducing x=5555 modulo n=257 with k=8. With this algorithm a single shift right at the end is the only right shift required to reduce the input instead of k right shifts inside the loop. Note that for the iterations t=2,5,6 and 8 where the result x is not changed. In those iterations the t'th bit of x is zero and the appropriate multiple of t does not need to be added to force the t'th bit of the result to zero.

6.3.1 Digit Based Montgomery Reduction

Instead of computing the reduction on a bit-by-bit basis it is actually much faster to compute it on digit-by-digit basis. Consider the previous algorithm re-written to compute the Montgomery reduction in this new fashion.

```
Algorithm Montgomery Reduction (modified II).

Input. Integer x, n and k
Output. \beta^{-k}x \pmod{n}

1. for t from 0 to k-1 do
1.1 x \leftarrow x + \mu n \beta^t
2. Return x/\beta^k.
```

Figure 6.7: Algorithm Montgomery Reduction (modified II)

The value $\mu n \beta^t$ is a multiple of the modulus n meaning that it will not change the residue. If the first digit of the value $\mu n \beta^t$ equals the negative (modulo β) of the t'th digit of x then the addition will result in a zero digit. This problem breaks down to solving the following congruency.

```
\begin{array}{rcl} x_t + \mu n_0 & \equiv & 0 \pmod{\beta} \\ \mu n_0 & \equiv & -x_t \pmod{\beta} \\ \mu & \equiv & -x_t/n_0 \pmod{\beta} \end{array}
```

In each iteration of the loop on step 1 a new value of μ must be calculated. The value of $-1/n_0 \pmod{\beta}$ is used extensively in this algorithm and should be precomputed. Let ρ represent the negative of the modular inverse of n_0 modulo β .

For example, let $\beta=10$ represent the radix. Let n=17 represent the modulus which implies k=2 and $\rho\equiv7$. Let x=33 represent the value to reduce.

Step (t)	Value of x	Value of μ
_	33	_
0	$33 + \mu n = 50$	1
1	$50 + \mu n\beta = 900$	5

Figure 6.8: Example of Montgomery Reduction

The final result 900 is then divided by β^k to produce the final result 9. The first observation is that $9 \not\equiv x \pmod{n}$ which implies the result is not the modular residue of x modulo n. However, recall that the residue is actually multiplied by β^{-k} in the algorithm. To get the true residue the value must be multiplied by β^k . In this case $\beta^k \equiv 15 \pmod{n}$ and the correct residue is $9 \cdot 15 \equiv 16 \pmod{n}$.

6.3.2 Baseline Montgomery Reduction

The baseline Montgomery reduction algorithm will produce the residue for any size input. It is designed to be a catch-all algororithm for Montgomery reductions.

```
Algorithm mp_montgomery_reduce.
Input. mp_int x, mp_int n and a digit \rho \equiv -1/n_0 \pmod{n}.
          (0 \le x < n^2, n > 1, (n, \beta) = 1, \beta^k > n)
Output. \beta^{-k}x \pmod{n}
1. digs \leftarrow 2n.used + 1
2. If digs < MP\_ARRAY and m.used < \delta then
  2.1 Use algorithm fast_mp_montgomery_reduce instead.
Setup x for the reduction.
3. If x.alloc < digs then grow x to digs digits.
4. x.used \leftarrow digs
Eliminate the lower k digits.
5. For ix from 0 to k-1 do
  5.1 \ \mu \leftarrow x_{ix} \cdot \rho \pmod{\beta}
  5.2 u \leftarrow 0
  5.3 For iy from 0 to k-1 do
     5.3.1 \ \hat{r} \leftarrow \mu n_{iy} + x_{ix+iy} + u
     5.3.2 \ x_{ix+iy} \leftarrow \hat{r} \ (\text{mod } \beta)
     5.3.3 \ u \leftarrow |\hat{r}/\beta|
  5.4 \text{ While } u > 0 \text{ do}
     5.4.1 \ iy \leftarrow iy + 1
     5.4.2 \ x_{ix+iy} \leftarrow x_{ix+iy} + u
     5.4.3 \ u \leftarrow |x_{ix+iy}/\beta|
     5.4.4 \ x_{ix+iy} \leftarrow x_{ix+iy} \ (\text{mod } \beta)
Divide by \beta^k and fix up as required.
6. x \leftarrow |x/\beta^k|
7. If x \geq n then
  7.1 \ x \leftarrow x - n
8. Return(MP\_OKAY).
```

Figure 6.9: Algorithm mp_montgomery_reduce

Algorithm mp_montgomery_reduce. This algorithm reduces the input x modulo n in place using the Montgomery reduction algorithm. The algorithm is loosely based on algorithm 14.32 of [2, pp.601] except it merges the multiplication of $\mu n \beta^t$ with the addition in the inner loop. The restrictions on this algorithm are fairly easy to adapt to. First $0 \le x < n^2$ bounds the input to

File: bn_mp_montgomery_reduce.c

numbers in the same range as for the Barrett algorithm. Additionally if n > 1 and n is odd there will exist a modular inverse ρ . ρ must be calculated in advance of this algorithm. Finally the variable k is fixed and a pseudonym for n.used.

Step 2 decides whether a faster Montgomery algorithm can be used. It is based on the Comba technique meaning that there are limits on the size of the input. This algorithm is discussed in sub-section 6.3.3.

Step 5 is the main reduction loop of the algorithm. The value of μ is calculated once per iteration in the outer loop. The inner loop calculates $x + \mu n \beta^{ix}$ by multiplying μn and adding the result to x shifted by ix digits. Both the addition and multiplication are performed in the same loop to save time and memory. Step 5.4 will handle any additional carries that escape the inner loop.

Using a quick inspection this algorithm requires n single precision multiplications for the outer loop and n^2 single precision multiplications in the inner loop. In total $n^2 + n$ single precision multiplications which compares favourably to Barrett at $n^2 + 2n - 1$ single precision multiplications.

```
016
017
      /* computes xR**-1 == x (mod N) via Montgomery Reduction */
018
019
     mp_montgomery_reduce (mp_int * x, mp_int * n, mp_digit rho)
020
021
        int
                ix, res, digs;
022
        mp_digit mu;
023
        /* can the fast reduction [comba] method be used?
024
025
026
         * Note that unlike in mp_mul you're safely allowed *less*
027
         * than the available columns [255 per default] since carries
028
         * are fixed up in the inner loop.
029
030
        digs = n->used * 2 + 1;
031
        if ((digs < MP_WARRAY) &&
032
            n->used <
            (1 << ((CHAR_BIT * sizeof (mp_word)) - (2 * DIGIT_BIT)))) {
033
034
          return fast_mp_montgomery_reduce (x, n, rho);
035
036
```

/* grow the input as required */

if (x->alloc < digs) {

037 038

```
039
          if ((res = mp_grow (x, digs)) != MP_OKAY) {
040
            return res;
041
          }
042
043
        x->used = digs;
044
        for (ix = 0; ix < n->used; ix++) {
045
046
          /* mu = ai * rho mod b
047
048
           * The value of rho must be precalculated via
049
           * bn_mp_montgomery_setup() such that
050
           * it equals -1/n0 \mod b this allows the
051
           * following inner loop to reduce the
052
           * input one digit at a time
053
           */
054
          mu = (mp_digit) (((mp_word)x->dp[ix]) * ((mp_word)rho) & MP_MASK);
055
056
          /* a = a + mu * m * b**i */
057
058
            register int iy;
            register mp_digit *tmpn, *tmpx, u;
059
060
            register mp_word r;
061
062
            /* alias for digits of the modulus */
063
            tmpn = n->dp;
064
065
            /* alias for the digits of x [the input] */
066
            tmpx = x->dp + ix;
067
068
            /* set the carry to zero */
            u = 0;
069
070
071
            /* Multiply and add in place */
            for (iy = 0; iy < n->used; iy++) {
072
              /* compute product and sum */
073
074
                      = ((mp_word)mu) * ((mp_word)*tmpn++) +
075
                        ((mp_word) u) + ((mp_word) * tmpx);
076
077
              /* get carry */
078
                      = (mp_digit)(r >> ((mp_word) DIGIT_BIT));
079
080
              /* fix digit */
```

```
*tmpx++ = (mp_digit)(r & ((mp_word) MP_MASK));
081
082
            /* At this point the ix'th digit of x should be zero */
083
084
085
            /* propagate carries upwards as required*/
086
            while (u) {
087
088
              *tmpx
                       += u:
089
                        = *tmpx >> DIGIT_BIT;
               *tmpx++ &= MP_MASK;
090
091
092
          }
093
        }
094
095
        /* at this point the n.used'th least
096
         * significant digits of x are all zero
097
         * which means we can shift x to the
098
         * right by n.used digits and the
099
         * residue is unchanged.
100
         */
101
        /* x = x/b**n.used */
102
103
        mp_clamp(x);
        mp_rshd (x, n->used);
104
105
106
        /* if x >= n then x = x - n */
107
        if (mp_cmp_mag (x, n) != MP_LT) {
108
          return s_mp_sub (x, n, x);
109
        }
110
111
        return MP_OKAY;
112
      }
```

This is the baseline implementation of the Montgomery reduction algorithm. Lines 30 to 35 determine if the Comba based routine can be used instead. Line 48 computes the value of μ for that particular iteration of the outer loop.

The multiplication $\mu n \beta^{ix}$ is performed in one step in the inner loop. The alias tmpx refers to the ix'th digit of x and the alias tmpn refers to the modulus n.

6.3.3 Faster "Comba" Montgomery Reduction

The Montgomery reduction requires fewer single precision multiplications than a Barrett reduction, however it is much slower due to the serial nature of the inner loop. The Barrett reduction algorithm requires two slightly modified multipliers which can be implemented with the Comba technique. The Montgomery reduction algorithm cannot directly use the Comba technique to any significant advantage since the inner loop calculates a $k \times 1$ product k times.

The biggest obstacle is that at the ix'th iteration of the outer loop the value of x_{ix} is required to calculate μ . This means the carries from 0 to ix - 1 must have been propagated upwards to form a valid ix'th digit. The solution as it turns out is very simple. Perform a Comba like multiplier and inside the outer loop just after the inner loop fix up the ix + 1'th digit by forwarding the carry.

With this change in place the Montgomery reduction algorithm can be performed with a Comba style multiplication loop which substantially increases the speed of the algorithm.

```
Algorithm fast_mp_montgomery_reduce.
Input. mp_int x, mp_int n and a digit \rho \equiv -1/n_0 \pmod{n}.
          (0 \le x < n^2, n > 1, (n, \beta) = 1, \beta^k > n)
Output. \beta^{-k}x \pmod{n}
Place an array of MP_WARRAY mp_word variables called \hat{W} on the stack.
1. if x.alloc < n.used + 1 then grow x to n.used + 1 digits.
Copy the digits of x into the array \hat{W}
2. For ix from 0 to x.used - 1 do
  2.1 \ \hat{W}_{ix} \leftarrow x_{ix}
3. For ix from x.used to 2n.used - 1 do
  3.1 \ \hat{W}_{ix} \leftarrow 0
Elimiate the lower k digits.
4. for ix from 0 to n.used - 1 do
  4.1 \ \mu \leftarrow \hat{W}_{ix} \cdot \rho \pmod{\beta}
  4.2 For iy from 0 to n.used - 1 do
     4.2.1 \ \hat{W}_{iy+ix} \leftarrow \hat{W}_{iy+ix} + \mu \cdot n_{iy}
  4.3 \ \hat{W}_{ix+1} \leftarrow \hat{W}_{ix+1} + |\hat{W}_{ix}/\beta|
Propagate carries upwards.
5. for ix from n.used to 2n.used + 1 do
  5.1 \ \hat{W}_{ix+1} \leftarrow \hat{W}_{ix+1} + |\hat{W}_{ix}/\beta|
Shift right and reduce modulo \beta simultaneously.
6. for ix from 0 to n.used + 1 do
  6.1 \ x_{ix} \leftarrow \hat{W}_{ix+n.used} \ (\text{mod } \beta)
Zero excess digits and fixup x.
7. if x.used > n.used + 1 then do
  7.1 for ix from n.used + 1 to x.used - 1 do
     7.1.1 \ x_{ix} \leftarrow 0
8. x.used \leftarrow n.used + 1
9. Clamp excessive digits of x.
10. If x \geq n then
  10.1 \ x \leftarrow x - n
11. Return(MP_{-}OKAY).
```

Figure 6.10: Algorithm fast_mp_montgomery_reduce

Algorithm fast_mp_montgomery_reduce. This algorithm will compute the Montgomery reduction of x modulo n using the Comba technique. It is on most computer platforms significantly faster than algorithm mp_montgomery_reduce and algorithm mp_reduce ($Barrett\ reduction$). The algorithm has the same re-

strictions on the input as the baseline reduction algorithm. An additional two restrictions are imposed on this algorithm. The number of digits k in the the modulus n must not violate $MP_WARRAY > 2k+1$ and $n < \delta$. When $\beta = 2^{28}$ this algorithm can be used to reduce modulo a modulus of at most 3,556 bits in length.

As in the other Comba reduction algorithms there is a W array which stores the columns of the product. It is initially filled with the contents of x with the excess digits zeroed. The reduction loop is very similar the to the baseline loop at heart. The multiplication on step 4.1 can be single precision only since $ab \pmod{\beta} \equiv (a \mod \beta)(b \mod \beta)$. Some multipliers such as those on the ARM processors take a variable length time to complete depending on the number of bytes of result it must produce. By performing a single precision multiplication instead half the amount of time is spent.

Also note that digit \hat{W}_{ix} must have the carry from the ix-1'th digit propagated upwards in order for this to work. That is what step 4.3 will do. In effect over the n.used iterations of the outer loop the n.used'th lower columns all have the their carries propagated forwards. Note how the upper bits of those same words are not reduced modulo β . This is because those values will be discarded shortly and there is no point.

Step 5 will propagate the remainder of the carries upwards. On step 6 the columns are reduced modulo β and shifted simultaneously as they are stored in the destination x.

```
File: bn_fast_mp_montgomery_reduce.c
016
017
      /* computes xR**-1 == x (mod N) via Montgomery Reduction
018
019
       * This is an optimized implementation of mp_montgomery_reduce
020
       * which uses the comba method to quickly calculate the columns of the
021
       * reduction.
022
023
       * Based on Algorithm 14.32 on pp.601 of HAC.
024
      */
025
026
      fast_mp_montgomery_reduce (mp_int * x, mp_int * n, mp_digit rho)
027
                ix, res, olduse;
028
029
        mp_word W[MP_WARRAY];
030
        /* get old used count */
031
032
        olduse = x->used;
```

```
033
034
        /* grow a as required */
035
        if (x->alloc < n->used + 1) {
036
          if ((res = mp\_grow (x, n->used + 1)) != MP\_OKAY) {
037
            return res;
038
039
        }
040
041
        /* first we have to get the digits of the input into
042
         * an array of double precision words W[\ldots]
043
         */
044
045
          register mp_word *_W;
046
          register mp_digit *tmpx;
047
048
          /* alias for the W[] array */
049
             = W;
050
051
          /* alias for the digits of x*/
052
          tmpx = x->dp;
053
054
          /* copy the digits of a into W[0..a->used-1] */
055
          for (ix = 0; ix < x->used; ix++) \{
056
            *_W++ = *tmpx++;
057
058
059
          /* zero the high words of W[a->used..m->used*2] */
060
          for (; ix < n-vec * 2 + 1; ix++) {
061
            *_W++ = 0;
062
063
        }
064
065
        /* now we proceed to zero successive digits
066
         * from the least significant upwards
067
068
        for (ix = 0; ix < n->used; ix++) {
          /* mu = ai * m' mod b
069
070
071
           * We avoid a double precision multiplication (which isn't required)
072
           * by casting the value down to a mp_digit. Note this requires
073
           * that W[ix-1] have the carry cleared (see after the inner loop)
074
           */
```

```
075
          register mp_digit mu;
076
          mu = (mp_digit) (((W[ix] & MP_MASK) * rho) & MP_MASK);
077
078
          /* a = a + mu * m * b**i
079
080
           * This is computed in place and on the fly. The multiplication
           \ast by b**i is handled by offseting which columns the results
081
082
           * are added to.
083
084
           * Note the comba method normally doesn't handle carries in the
085
           * inner loop In this case we fix the carry from the previous
086
           st column since the Montgomery reduction requires digits of the
087
           * result (so far) [see above] to work. This is
           * handled by fixing up one carry after the inner loop.
880
089
           * carry fixups are done in order so after these loops the
090
           * first m->used words of W[] have the carries fixed
091
           */
092
093
            register int iy;
094
            register mp_digit *tmpn;
095
            register mp_word *_W;
096
097
            /* alias for the digits of the modulus */
098
            tmpn = n->dp;
099
100
            /* Alias for the columns set by an offset of ix */
101
            _W = W + ix;
102
103
            /* inner loop */
104
            for (iy = 0; iy < n->used; iy++) {
105
                *_W++ += ((mp_word)mu) * ((mp_word)*tmpn++);
106
107
          }
108
109
          /* now fix carry for next digit, W[ix+1] */
110
          W[ix + 1] += W[ix] >> ((mp_word) DIGIT_BIT);
111
112
113
        /* now we have to propagate the carries and
         * shift the words downward [all those least
114
         * significant digits we zeroed].
115
116
         */
```

```
117
118
          register mp_digit *tmpx;
          register mp_word *_W, *_W1;
119
120
121
          /* nox fix rest of carries */
122
          /* alias for current word */
123
124
          _W1 = W + ix;
125
126
          /* alias for next word, where the carry goes */
127
          _W = W + ++ix;
128
129
          for (; ix \le n-vsed * 2 + 1; ix++) {
            *_W++ += *_W1++ >> ((mp_word) DIGIT_BIT);
130
131
132
133
          /* copy out, A = A/b**n
134
135
           * The result is A/b**n but instead of converting from an
136
           * array of mp_word to mp_digit than calling mp_rshd
137
           * we just copy them in the right order
138
           */
139
140
          /* alias for destination word */
          tmpx = x->dp;
141
142
143
          /* alias for shifted double precision result */
144
          _W = W + n -> used;
145
146
          for (ix = 0; ix < n->used + 1; ix++) {
147
            *tmpx++ = (mp_digit)(*_W++ & ((mp_word) MP_MASK));
148
149
150
          /* zero oldused digits, if the input a was larger than
151
           * m->used+1 we'll have to clear the digits
152
           */
153
          for (; ix < olduse; ix++) {
            *tmpx++ = 0;
154
155
        }
156
157
158
        /* set the max used and clamp */
```

```
159     x->used = n->used + 1;
160     mp_clamp (x);
161
162     /* if A >= m then A = A - m */
163     if (mp_cmp_mag (x, n) != MP_LT) {
        return s_mp_sub (x, n, x);
165     }
166     return MP_OKAY;
167  }
```

The \hat{W} array is first filled with digits of x on line 48 then the rest of the digits are zeroed on line 55. Both loops share the same alias variables to make the code easier to read.

The value of μ is calculated in an interesting fashion. First the value \hat{W}_{ix} is reduced modulo β and cast to a mp_digit. This forces the compiler to use a single precision multiplication and prevents any concerns about loss of precision. Line 110 fixes the carry for the next iteration of the loop by propagating the carry from \hat{W}_{ix} to \hat{W}_{ix+1} .

The for loop on line 109 propagates the rest of the carries upwards through the columns. The for loop on line 126 reduces the columns modulo β and shifts them k places at the same time. The alias \hat{W} actually refers to the array \hat{W} starting at the n.used'th digit, that is $\hat{W}_t = \hat{W}_{n.used+t}$.

6.3.4 Montgomery Setup

To calculate the variable ρ a relatively simple algorithm will be required.

```
Algorithm mp_montgomery_setup.
Input. mp_int n \ (n > 1 \text{ and } (n, 2) = 1)
Output. \rho \equiv -1/n_0 \pmod{\beta}

1. b \leftarrow n_0
2. If b is even return(MP\_VAL)
3. x \leftarrow ((b+2) \text{ AND } 4) << 1) + b
4. for k from 0 to \lceil lg(lg(\beta)) \rceil - 2 do
4.1 x \leftarrow x \cdot (2 - bx)
5. \rho \leftarrow \beta - x \pmod{\beta}
6. Return(MP\_OKAY).
```

Figure 6.11: Algorithm mp_montgomery_setup

Algorithm mp_montgomery_setup. This algorithm will calculate the value of ρ required within the Montgomery reduction algorithms. It uses a very interesting trick to calculate $1/n_0$ when β is a power of two.

```
File: bn_mp_montgomery_setup.c
016
017
      /* setups the montgomery reduction stuff */
018
019
      mp_montgomery_setup (mp_int * n, mp_digit * rho)
020
021
       mp_digit x, b;
022
023
      /* fast inversion mod 2**k
024
025
       * Based on the fact that
026
       * XA = 1 \pmod{2**n} \Rightarrow (X(2-XA)) A = 1 \pmod{2**2n}
027
028
                            => 2*X*A - X*X*A*A = 1
029
                            => 2*(1) - (1)
030
031
      b = n->dp[0];
032
033
        if ((b & 1) == 0) {
034
         return MP_VAL;
035
        }
036
037
        x = (((b + 2) & 4) << 1) + b; /* here x*a==1 mod 2**4 */
                                      /* here x*a==1 mod 2**8 */
038
        x *= 2 - b * x;
039
      #if !defined(MP_8BIT)
040
        x *= 2 - b * x;
                                      /* here x*a==1 mod 2**16 */
041
      #endif
042
      #if defined(MP_64BIT) || !(defined(MP_8BIT) || defined(MP_16BIT))
043
        x *= 2 - b * x;
                                      /* here x*a==1 mod 2**32 */
044
      #endif
045
      #ifdef MP_64BIT
                                      /* here x*a==1 mod 2**64 */
046
        x *= 2 - b * x;
047
      #endif
048
        /* rho = -1/m mod b */
049
050
        *rho = (((mp_digit) 1 << ((mp_digit) DIGIT_BIT)) - x) & MP_MASK;
051
052
       return MP_OKAY;
```

053 }

This source code computes the value of ρ required to perform Montgomery reduction. It has been modified to avoid performing excess multiplications when β is not the default 28-bits.

6.4 The Diminished Radix Algorithm

The Diminished Radix method of modular reduction [9] is a fairly clever technique which can be more efficient than either the Barrett or Montgomery methods for certain forms of moduli. The technique is based on the following simple congruence.

$$(x \bmod n) + k|x/n| \equiv x \pmod{(n-k)} \tag{6.6}$$

This observation was used in the MMB [10] block cipher to create a diffusion primitive. It used the fact that if $n=2^{31}$ and k=1 that then a x86 multiplier could produce the 62-bit product and use the "shrd" instruction to perform a double-precision right shift. The proof of the above equation is very simple. First write x in the product form.

$$x = qn + r \tag{6.7}$$

Now reduce both sides modulo (n-k).

$$x \equiv qk + r \pmod{(n-k)} \tag{6.8}$$

The variable n reduces modulo n-k to k. By putting $q=\lfloor x/n\rfloor$ and r=x mod n into the equation the original congruence is reproduced, thus concluding the proof. The following algorithm is based on this observation.

This algorithm will reduce x modulo n-k and return the residue. If $0 \le x < (n-k)^2$ then the algorithm will loop almost always once or twice and occasionally three times. For simplicity sake the value of x is bounded by the following simple polynomial.

$$0 \le x < n^2 + k^2 - 2nk \tag{6.9}$$

The true bound is $0 \le x < (n-k-1)^2$ but this has quite a few more terms. The value of q after step 1 is bounded by the following.

$$q < n - 2k - k^2/n (6.10)$$

5.2 Goto step 1.

6. Return x

```
Algorithm Diminished Radix Reduction. Input. Integer x, n, k Output. x \mod (n-k)

1. q \leftarrow \lfloor x/n \rfloor
2. q \leftarrow k \cdot q
3. x \leftarrow x \pmod n
4. x \leftarrow x + q
5. If x \ge (n-k) then
5.1 x \leftarrow x - (n-k)
```

Figure 6.12: Algorithm Diminished Radix Reduction

Since k^2 is going to be considerably smaller than n that term will always be zero. The value of x after step 3 is bounded trivially as $0 \le x < n$. By step four the sum x + q is bounded by

$$0 \le q + x < (k+1)n - 2k^2 - 1 \tag{6.11}$$

With a second pass q will be loosely bounded by $0 \le q < k^2$ after step 2 while x will still be loosely bounded by $0 \le x < n$ after step 3. After the second pass it is highly unlike that the sum in step 4 will exceed n - k. In practice fewer than three passes of the algorithm are required to reduce virtually every input in the range $0 \le x < (n - k - 1)^2$.

Figure 6.13 demonstrates the reduction of x=123456789 modulo n-k=253 when n=256 and k=3. Note that even while x is considerably larger than $(n-k-1)^2=63504$ the algorithm still converges on the modular residue exceedingly fast. In this case only three passes were required to find the residue $x\equiv 126$.

6.4.1 Choice of Moduli

On the surface this algorithm looks like a very expensive algorithm. It requires a couple of subtractions followed by multiplication and other modular reductions. The usefulness of this algorithm becomes exceedingly clear when an appropriate modulus is chosen.

```
x = 123456789, n = 256, k = 3
q \leftarrow |x/n| = 482253
q \leftarrow q * k = 1446759
x \leftarrow x \mod n = 21
x \leftarrow x + q = 1446780
x \leftarrow x - (n - k) = 1446527
q \leftarrow |x/n| = 5650
q \leftarrow q * k = 16950
x \leftarrow x \bmod n = 127
x \leftarrow x + q = 17077
x \leftarrow x - (n - k) = 16824
q \leftarrow |x/n| = 65
q \leftarrow q * k = 195
x \leftarrow x \mod n = 184
x \leftarrow x + q = 379
x \leftarrow x - (n - k) = 126
```

Figure 6.13: Example Diminished Radix Reduction

Division in general is a very expensive operation to perform. The one exception is when the division is by a power of the radix of representation used. Division by ten for example is simple for pencil and paper mathematics since it amounts to shifting the decimal place to the right. Similarly division by two (or powers of two) is very simple for binary computers to perform. It would therefore seem logical to choose n of the form 2^p which would imply that $\lfloor x/n \rfloor$ is a simple shift of x right p bits.

However, there is one operation related to division of power of twos that is even faster than this. If $n = \beta^p$ then the division may be performed by moving whole digits to the right p places. In practice division by β^p is much faster than division by 2^p for any p. Also with the choice of $n = \beta^p$ reducing x modulo n merely requires zeroing the digits above the p-1'th digit of x.

Throughout the next section the term "restricted modulus" will refer to a modulus of the form $\beta^p - k$ whereas the term "unrestricted modulus" will refer to a modulus of the form $2^p - k$. The word "restricted" in this case refers to the fact that it is based on the 2^p logic except p must be a multiple of $lg(\beta)$.

6.4.2 Choice of k

Now that division and reduction (step 1 and 3 of figure 6.12) have been optimized to simple digit operations the multiplication by k in step 2 is the most expensive operation. Fortunately the choice of k is not terribly limited. For all intents and purposes it might as well be a single digit. The smaller the value of k is the faster the algorithm will be.

6.4.3 Restricted Diminished Radix Reduction

The restricted Diminished Radix algorithm can quickly reduce an input modulo a modulus of the form $n = \beta^p - k$. This algorithm can reduce an input x within the range $0 \le x < n^2$ using only a couple passes of the algorithm demonstrated in figure 6.12. The implementation of this algorithm has been optimized to avoid additional overhead associated with a division by β^p , the multiplication by k or the addition of x and q. The resulting algorithm is very efficient and can lead to substantial improvements over Barrett and Montgomery reduction when modular exponentiations are performed.

```
Algorithm mp_dr_reduce.
Input. mp_int x, n and a mp_digit k = \beta - n_0
          (0 \le x < n^2, n > 1, 0 < k < \beta)
Output. x \mod n
1. m \leftarrow n.used
2. If x.alloc < 2m then grow x to 2m digits.
3. \mu \leftarrow 0
4. for i from 0 to m-1 do
  4.1 \ \hat{r} \leftarrow k \cdot x_{m+i} + x_i + \mu
  4.2 \ x_i \leftarrow \hat{r} \ (\text{mod } \beta)
  4.3 \ \mu \leftarrow |\hat{r}/\beta|
5. x_m \leftarrow \mu
6. for i from m+1 to x.used-1 do
  6.1 \ x_i \leftarrow 0
7. Clamp excess digits of x.
8. If x > n then
  8.1 \ x \leftarrow x - n
  8.2 Goto step 3.
9. Return(MP\_OKAY).
```

Figure 6.14: Algorithm mp_dr_reduce

Algorithm mp_dr_reduce. This algorithm will perform the Dimished Radix reduction of x modulo n. It has similar restrictions to that of the Barrett reduction with the addition that n must be of the form $n = \beta^m - k$ where $0 < k < \beta$.

This algorithm essentially implements the pseudo-code in figure 6.12 except with a slight optimization. The division by β^m , multiplication by k and addition of $x \mod \beta^m$ are all performed simultaneously inside the loop on step 4. The division by β^m is emulated by accessing the term at the m+i'th position which is subsequently multiplied by k and added to the term at the i'th position. After the loop the m'th digit is set to the carry and the upper digits are zeroed. Steps 5 and 6 emulate the reduction modulo β^m that should have happend to x before the addition of the multiple of the upper half.

At step 8 if x is still larger than n another pass of the algorithm is required. First n is subtracted from x and then the algorithm resumes at step 3.

```
File: bn_mp_dr_reduce.c 016 /* reduce "x" in place modulo "n" using the Diminished Radix algorithm.
```

```
018
019
       * Based on algorithm from the paper
020
021
       * "Generating Efficient Primes for Discrete Log Cryptosystems"
022
                         Chae Hoon Lim, Pil Loong Lee,
023
                  POSTECH Information Research Laboratories
024
025
       * The modulus must be of a special format [see manual]
026
027
       * Has been modified to use algorithm 7.10 from the LTM book instead
028
029
       * Input x must be in the range 0 \le x \le (n-1)**2
030
       */
031
      int
032
      mp_dr_reduce (mp_int * x, mp_int * n, mp_digit k)
033
034
        int
                 err, i, m;
035
       mp_word r;
036
        mp_digit mu, *tmpx1, *tmpx2;
037
038
        /* m = digits in modulus */
039
       m = n->used;
040
041
        /* ensure that "x" has at least 2m digits */
042
        if (x->alloc < m + m) {
043
          if ((err = mp_grow (x, m + m)) != MP_OKAY) {
044
            return err;
045
046
        }
047
048
      /* top of loop, this is where the code resumes if
049
       * another reduction pass is required.
050
051
      top:
052
       /* aliases for digits */
053
        /* alias for lower half of x */
054
       tmpx1 = x->dp;
055
056
        /* alias for upper half of x, or x/B**m */
057
        tmpx2 = x->dp + m;
058
059
       /* set carry to zero */
```

```
060
        mu = 0;
061
        /* compute (x mod B**m) + k * [x/B**m] inline and inplace */
062
063
        for (i = 0; i < m; i++) {
                       = ((mp_word)*tmpx2++) * ((mp_word)k) + *tmpx1 + mu;
064
            r
065
            *tmpx1++ = (mp_digit)(r & MP_MASK);
066
                      = (mp_digit)(r >> ((mp_word)DIGIT_BIT));
067
        }
068
069
        /* set final carry */
070
        *tmpx1++ = mu;
071
072
        /* zero words above m */
073
        for (i = m + 1; i < x-)used; i++) {
074
            *tmpx1++ = 0;
075
076
077
        /* clamp, sub and return */
078
        mp_clamp (x);
079
080
        /* if x >= n then subtract and reduce again
081
         * Each successive "recursion" makes the input smaller and smaller.
         */
082
083
        if (mp_cmp_mag(x, n) != MP_LT) {
084
          s_mp_sub(x, n, x);
085
          goto top;
086
087
        return MP_OKAY;
088
      }
```

The first step is to grow x as required to 2m digits since the reduction is performed in place on x. The label on line 51 is where the algorithm will resume if further reduction passes are required. In theory it could be placed at the top of the function however, the size of the modulus and question of whether x is large enough are invariant after the first pass meaning that it would be a waste of time.

The aliases tmpx1 and tmpx2 refer to the digits of x where the latter is offset by m digits. By reading digits from x offset by m digits a division by β^m can be simulated virtually for free. The loop on line 63 performs the bulk of the work (corresponds to step 4 of algorithm 7.11) in this algorithm.

By line 70 the pointer tmpx1 points to the m'th digit of x which is where the final carry will be placed. Similarly by line 73 the same pointer will point

to the m + 1'th digit where the zeroes will be placed.

Since the algorithm is only valid if both x and n are greater than zero an unsigned comparison suffices to determine if another pass is required. With the same logic at line 84 the value of x is known to be greater than or equal to n meaning that an unsigned subtraction can be used as well. Since the destination of the subtraction is the larger of the inputs the call to algorithm s_mp_sub cannot fail and the return code does not need to be checked.

Setup

To setup the restricted Diminished Radix algorithm the value $k = \beta - n_0$ is required. This algorithm is not really complicated but provided for completeness.

```
Algorithm mp_dr_setup.
Input. mp_int n
Output. k = \beta - n_0

1. k \leftarrow \beta - n_0
```

Figure 6.15: Algorithm mp_dr_setup

```
File: bn_mp_dr_setup.c
016
017
      /* determines the setup value */
018
      void mp_dr_setup(mp_int *a, mp_digit *d)
019
020
         /* the casts are required if DIGIT_BIT is one less than
021
          * the number of bits in a mp_digit [e.g. DIGIT_BIT==31]
022
023
         *d = (mp_digit)((((mp_word)1) << ((mp_word)DIGIT_BIT)) -
              ((mp_word)a->dp[0]));
024
025
      }
026
```

Modulus Detection

Another algorithm which will be useful is the ability to detect a restricted Diminished Radix modulus. An integer is said to be of restricted Diminished Radix form if all of the digits are equal to $\beta-1$ except the trailing digit which may be any value.

```
Algorithm mp_dr_is_modulus.

Input. mp_int n
Output. 1 if n is in D.R form, 0 otherwise

1. If n.used < 2 then return(0).

2. for ix from 1 to n.used - 1 do

2.1 If n_{ix} \neq \beta - 1 return(0).

3. Return(1).
```

Figure 6.16: Algorithm mp_dr_is_modulus

Algorithm mp_dr_is_modulus. This algorithm determines if a value is in Diminished Radix form. Step 1 rejects obvious cases where fewer than two digits are in the mp_int. Step 2 tests all but the first digit to see if they are equal to $\beta - 1$. If the algorithm manages to get to step 3 then n must be of Diminished Radix form.

File: bn_mp_dr_is_modulus.c

```
016
017
      /* determines if a number is a valid DR modulus */
      int mp_dr_is_modulus(mp_int *a)
018
019
020
         int ix;
021
         /* must be at least two digits */
022
023
         if (a->used < 2) {
024
            return 0;
025
026
027
         /* must be of the form b**k - a [a \le b] so all
028
          * but the first digit must be equal to -1 (mod b).
029
          */
030
         for (ix = 1; ix < a->used; ix++) \{
031
             if (a->dp[ix] != MP_MASK) {
032
                return 0;
033
034
035
         return 1;
036
      }
037
```

6.4.4 Unrestricted Diminished Radix Reduction

The unrestricted Diminished Radix algorithm allows modular reductions to be performed when the modulus is of the form $2^p - k$. This algorithm is a straightforward adaptation of algorithm 6.12.

In general the restricted Diminished Radix reduction algorithm is much faster since it has considerably lower overhead. However, this new algorithm is much faster than either Montgomery or Barrett reduction when the moduli are of the appropriate form.

```
Algorithm mp_reduce_2k.

Input. mp_int a and n. mp_digit k
(a \geq 0, n > 1, 0 < k < \beta, n + k \text{ is a power of two})
Output. a \pmod{n}
1. \ p \leftarrow \lceil lg(n) \rceil \ (mp\_count\_bits)
2. While a \geq n do
2.1 \ q \leftarrow \lfloor a/2^p \rfloor \ (mp\_div\_2d)
2.2 \ a \leftarrow a \pmod{2^p} \ (mp\_mod\_2d)
2.3 \ q \leftarrow q \cdot k \ (mp\_mul\_d)
2.4 \ a \leftarrow a - q \ (s\_mp\_sub)
2.5 \ \text{If } a \geq n \ \text{then do}
2.5.1 \ a \leftarrow a - n
3. Return(MP\_OKAY).
```

Figure 6.17: Algorithm mp_reduce_2k

Algorithm mp_reduce_2k. This algorithm quickly reduces an input a modulo an unrestricted Diminished Radix modulus n. Division by 2^p is emulated with a right shift which makes the algorithm fairly inexpensive to use.

```
File: bn_mp_reduce_2k.c
016
017
      /* reduces a modulo n where n is of the form 2**p - k */
018
019
      mp_reduce_2k(mp_int *a, mp_int *n, mp_digit k)
020
021
         mp_int q;
022
         int
                p, res;
023
         if ((res = mp_init(&q)) != MP_OKAY) {
024
025
            return res;
```

```
}
026
027
028
         p = mp_count_bits(n);
029
030
         /* q = a/2**p, a = a mod 2**p */
031
         if ((res = mp_div_2d(a, p, &q, a)) != MP_OKAY) {
032
             goto ERR;
033
034
         if (k != 1) {
035
036
             /* q = q * k */
             if ((res = mp_mul_d(&q, k, &q)) != MP_OKAY) \{
037
038
                goto ERR;
039
040
         }
041
042
         /* a = a + q */
043
         if ((res = s_mp_add(a, &q, a)) != MP_OKAY) {
044
             goto ERR;
         }
045
046
047
         if (mp_cmp_mag(a, n) != MP_LT) {
            s_mp_sub(a, n, a);
048
049
            goto top;
         }
050
051
052
      ERR:
053
         mp_clear(&q);
054
         return res;
055
      }
056
```

The algorithm mp_count_bits calculates the number of bits in an mp_int which is used to find the initial value of p. The call to mp_div_2d on line 31 calculates both the quotient q and the remainder a required. By doing both in a single function call the code size is kept fairly small. The multiplication by k is only performed if k > 1. This allows reductions modulo $2^p - 1$ to be performed without any multiplications.

The unsigned s_mp_add, mp_cmp_mag and s_mp_sub are used in place of their full sign counterparts since the inputs are only valid if they are positive. By using the unsigned versions the overhead is kept to a minimum.

Unrestricted Setup

To setup this reduction algorithm the value of $k = 2^p - n$ is required.

```
Algorithm mp_reduce_2k_setup.

Input. mp_int n

Output. k = 2^p - n

1. p \leftarrow \lceil lg(n) \rceil \ (mp\_count\_bits)

2. x \leftarrow 2^p \ (mp\_2expt)

3. x \leftarrow x - n \ (mp\_sub)

4. k \leftarrow x_0

5. Return(MP\_OKAY).
```

Figure 6.18: Algorithm mp_reduce_2k_setup

Algorithm mp_reduce_2k_setup. This algorithm computes the value of k required for the algorithm mp_reduce_2k. By making a temporary variable x equal to 2^p a subtraction is sufficient to solve for k. Alternatively if n has more than one digit the value of k is simply $\beta - n_0$.

```
File: bn_mp_reduce_2k_setup.c
017
      /* determines the setup value */
018
019
      mp_reduce_2k_setup(mp_int *a, mp_digit *d)
020
021
         int res, p;
022
         mp_int tmp;
023
024
         if ((res = mp_init(&tmp)) != MP_OKAY) {
025
            return res;
026
         }
027
028
         p = mp_count_bits(a);
         if ((res = mp_2expt(&tmp, p)) != MP_OKAY) {
029
030
            mp_clear(&tmp);
031
            return res;
032
033
034
         if ((res = s_mp_sub(&tmp, a, &tmp)) != MP_OKAY) {
035
            mp_clear(&tmp);
036
            return res;
```

```
037 }
038
039 *d = tmp.dp[0];
040 mp_clear(&tmp);
041 return MP_OKAY;
042 }
```

Unrestricted Detection

An integer n is a valid unrestricted Diminished Radix modulus if either of the following are true.

- 1. The number has only one digit.
- 2. The number has more than one digit and every bit from the β 'th to the most significant is one.

If either condition is true than there is a power of two 2^p such that $0 < 2^p - n < \beta$. If the input is only one digit than it will always be of the correct form. Otherwise all of the bits above the first digit must be one. This arises from the fact that there will be value of k that when added to the modulus causes a carry in the first digit which propagates all the way to the most significant bit. The resulting sum will be a power of two.

```
Algorithm mp_reduce_is_2k.

Input. mp_int n

Output. 1 if of proper form, 0 otherwise

1. If n.used = 0 then return(0).
2. If n.used = 1 then return(1).
3. p \leftarrow \lceil lg(n) \rceil (mp\_count\_bits)
4. for x from lg(\beta) to p do
4.1 If the (x \mod lg(\beta))'th bit of the \lfloor x/lg(\beta) \rfloor of n is zero then return(0).
5. Return(1).
```

Figure 6.19: Algorithm mp_reduce_is_2k

Algorithm mp_reduce_is_2k. This algorithm quickly determines if a modulus is of the form required for algorithm mp_reduce_2k to function properly.

File: bn_mp_reduce_is_2k.c

```
016
017
      /* determines if mp_reduce_2k can be used */
018
      int mp_reduce_is_2k(mp_int *a)
019
020
         int ix, iy, iz, iw;
021
         if (a->used == 0) {
022
023
             return 0;
         } else if (a->used == 1) {
024
025
            return 1;
         } else if (a->used > 1) {
026
             iy = mp_count_bits(a);
027
028
             iz = 1;
             iw = 1;
029
030
031
             /* Test every bit from the second digit up, must be 1 */
032
            for (ix = DIGIT_BIT; ix < iy; ix++) {</pre>
033
                 if ((a->dp[iw] \& iz) == 0) {
034
                    return 0;
                 }
035
036
                 iz <<= 1;
037
                 if (iz > (int)MP_MASK) {
038
                    ++iw;
039
                    iz = 1;
040
             }
041
042
043
         return 1;
044
045
```

6.5 Algorithm Comparison

So far three very different algorithms for modular reduction have been discussed. Each of the algorithms have their own strengths and weaknesses that makes having such a selection very useful. The following table sumarizes the three algorithms along with comparisons of work factors. Since all three algorithms have the restriction that $0 \le x < n^2$ and n > 1 those limitations are not included in the table.

Method	Work Required	Limitations	m = 8	m = 32	m = 64
Barrett	$m^2 + 2m - 1$	None	79	1087	4223
Montgomery	$m^2 + m$	n must be odd	72	1056	4160
D.R.	2m	$n = \beta^m - k$	16	64	128

In theory Montgomery and Barrett reductions would require roughly the same amount of time to complete. However, in practice since Montgomery reduction can be written as a single function with the Comba technique it is much faster. Barrett reduction suffers from the overhead of calling the half precision multipliers, addition and division by β algorithms.

For almost every cryptographic algorithm Montgomery reduction is the algorithm of choice. The one set of algorithms where Diminished Radix reduction truly shines are based on the discrete logarithm problem such as Diffie-Hellman [?] and ElGamal [?]. In these algorithms primes of the form $\beta^m - k$ can be found and shared amongst users. These primes will allow the Diminished Radix algorithm to be used in modular exponentiation to greatly speed up the operation.

Exercises

- [3] Prove that the "trick" in algorithm mp_montgomery_setup actually calculates the correct value of ρ .
- [2] Devise an algorithm to reduce modulo n + k for small k quickly.
- [4] Prove that the pseudo-code algorithm "Diminished Radix Reduction" (figure 6.12) terminates. Also prove the probability that it will terminate within $1 \le k \le 10$ iterations.

Chapter 7

Exponentiation

Exponentiation is the operation of raising one variable to the power of another, for example, a^b . A variant of exponentiation, computed in a finite field or ring, is called modular exponentiation. This latter style of operation is typically used in public key cryptosystems such as RSA and Diffie-Hellman. The ability to quickly compute modular exponentiations is of great benefit to any such cryptosystem and many methods have been sought to speed it up.

7.1 Exponentiation Basics

A trivial algorithm would simply multiply a against itself b-1 times to compute the exponentiation desired. However, as b grows in size the number of multiplications becomes prohibitive. Imagine what would happen if $b \sim 2^{1024}$ as is the case when computing an RSA signature with a 1024-bit key. Such a calculation could never be completed as it would take simply far too long.

Fortunately there is a very simple algorithm based on the laws of exponents. Recall that $lg_a(a^b) = b$ and that $lg_a(a^ba^c) = b + c$ which are two trivial relationships between the base and the exponent. Let b_i represent the *i*'th bit of *b* starting from the least significant bit. If *b* is a *k*-bit integer than the following equation is true.

$$a^b = \prod_{i=0}^{k-1} a^{2^i \cdot b_i} \tag{7.1}$$

By taking the base a logarithm of both sides of the equation the following equation is the result.

$$b = \sum_{i=0}^{k-1} 2^i \cdot b_i \tag{7.2}$$

The term a^{2^i} can be found from the i-1'th term by squaring the term since $\left(a^{2^i}\right)^2$ is equal to $a^{2^{i+1}}$. This observation forms the basis of essentially all fast exponentiation algorithms. It requires k squarings and on average $\frac{k}{2}$ multiplications to compute the result. This is indeed quite an improvement over simply multiplying by a a total of b-1 times.

While this current method is a considerable speed up there are further improvements to be made. For example, the a^{2^i} term does not need to be computed in an auxiliary variable. Consider the following equivalent algorithm.

```
Algorithm Left to Right Exponentiation. Input. Integer a, b and k Output. c = a^b

1. c \leftarrow 1
2. for i from k - 1 to 0 do

2.1 c \leftarrow c^2
2.2 c \leftarrow c \cdot a^{b_i}
3. Return c.
```

Figure 7.1: Left to Right Exponentiation

This algorithm starts from the most significant bit and works towards the least significant bit. When the i'th bit of b is set a is multiplied against the current product. In each iteration the product is squared which doubles the exponent of the individual terms of the product.

For example, let $b = 101100_2 \equiv 44_{10}$. The following chart demonstrates the actions of the algorithm.

Value of i	Value of c
-	1
5	a
4	a^2
3	$a^4 \cdot a$
2	$a^8 \cdot a^2 \cdot a$
1	$a^{16} \cdot a^4 \cdot a^2$
0	$a^{32} \cdot a^8 \cdot a^4$

Figure 7.2: Example of Left to Right Exponentiation

When the product $a^{32} \cdot a^8 \cdot a^4$ is simplified it is equal a^{44} which is the desired exponentiation. This particular algorithm is called "Left to Right" because it reads the exponent in that order. All of the exponentiation algorithms that will be presented are of this nature.

7.1.1 Single Digit Exponentiation

The first algorithm in the series of exponentiation algorithms will be an unbounded algorithm where the exponent is a single digit. It is intended to be used when a small power of an input is required (e.g. a^5). It is faster than simply multiplying b-1 times for all values of b that are greater than three.

```
Algorithm mp_expt_d.

Input. mp_int a and mp_digit b

Output. c = a^b

1. g \leftarrow a (mp\_init\_copy)
2. c \leftarrow 1 (mp\_set)
3. for x from 1 to lg(\beta) do
3.1 c \leftarrow c^2 (mp\_sqr)
3.2 If b AND 2^{lg(\beta)-1} \neq 0 then
3.2.1 c \leftarrow c \cdot g (mp\_mul)
3.3 b \leftarrow b < 1
4. Clear g.
5. Return(MP\_OKAY).
```

Figure 7.3: Algorithm mp_expt_d

Algorithm mp_expt_d. This algorithm computes the value of a raised to the power of a single digit b. It uses the left to right exponentiation algorithm to quickly compute the exponentiation. It is loosely based on algorithm 14.79 of HAC [2, pp. 615] with the difference that the exponent is a fixed width.

A copy of a is made first to allow destination variable c be the same as the source variable a. The result is set to the initial value of 1 in the subsequent step.

Inside the loop the exponent is read from the most significant bit first down to the least significant bit. First c is invariably squared on step 3.1. In the following step if the most significant bit of b is one the copy of a is multiplied against c. The value of b is shifted left one bit to make the next bit down from the most significant bit the new most significant bit. In effect each iteration of the loop moves the bits of the exponent b upwards to the most significant location.

```
File: bn_mp_expt_d.c
016
017  /* calculate c = a**b using a square-multiply algorithm */
018  int mp_expt_d (mp_int * a, mp_digit b, mp_int * c)
019  {
020    int    res, x;
021    mp_int g;
022
023    if ((res = mp_init_copy (&g, a)) != MP_OKAY) {
```

```
024
          return res;
025
026
027
        /* set initial result */
028
        mp_set (c, 1);
029
        for (x = 0; x < (int) DIGIT_BIT; x++) {
030
          /* square */
031
          if ((res = mp_sqr (c, c)) != MP_OKAY) {
032
033
            mp_clear (&g);
034
            return res;
035
036
          /* if the bit is set multiply */
037
038
          if ((b & (mp_digit) (((mp_digit)1) << (DIGIT_BIT - 1))) != 0) {
039
            if ((res = mp_mul (c, &g, c)) != MP_OKAY) {
040
                mp_clear (&g);
041
               return res;
042
            }
043
044
045
          /* shift to next bit */
046
          b <<= 1;
047
048
049
        mp_clear (&g);
050
        return MP_OKAY;
051
```

Line 28 sets the initial value of the result to 1. Next the loop on line 30 steps through each bit of the exponent starting from the most significant down towards the least significant. The invariant squaring operation placed on line 32 is performed first. After the squaring the result c is multiplied by the base g if and only if the most significant bit of the exponent is set. The shift on line 46 moves all of the bits of the exponent upwards towards the most significant location.

7.2 k-ary Exponentiation

When calculating an exponentiation the most time consuming bottleneck is the multiplications which are in general a small factor slower than squaring. Recall

from the previous algorithm that b_i refers to the i'th bit of the exponent b. Suppose instead it referred to the i'th k-bit digit of the exponent of b. For k=1 the definitions are synonymous and for k>1 algorithm 7.4 computes the same exponentiation. A group of k bits from the exponent is called a window. That is it is a small window on only a portion of the entire exponent. Consider the following modification to the basic left to right exponentiation algorithm.

```
Algorithm k-ary Exponentiation.

Input. Integer a, b, k and t

Output. c = a^b

1. c \leftarrow 1
2. for i from t - 1 to 0 do

2.1 c \leftarrow c^{2^k}
2.2 Extract the i'th k-bit word from b and store it in g.

2.3 c \leftarrow c \cdot a^g
3. Return c.
```

Figure 7.4: k-ary Exponentiation

The squaring on step 2.1 can be calculated by squaring the value c successively k times. If the values of a^g for $0 < g < 2^k$ have been precomputed this algorithm requires only t multiplications and tk squarings. The table can be generated with $2^{k-1}-1$ squarings and $2^{k-1}+1$ multiplications. This algorithm assumes that the number of bits in the exponent is evenly divisible by k. However, when it is not the remaining $0 < x \le k-1$ bits can be handled with algorithm 7.1.

Suppose k=4 and t=100. This modified algorithm will require 109 multiplications and 408 squarings to compute the exponentiation. The original algorithm would on average have required 200 multiplications and 400 squrings to compute the same value. The total number of squarings has increased slightly but the number of multiplications has nearly halved.

7.2.1 Optimal Values of k

An optimal value of k will minimize $2^k + \lceil n/k \rceil + n - 1$ for a fixed number of bits in the exponent n. The simplest approach is to brute force search amongst the values $k = 2, 3, \ldots, 8$ for the lowest result. Table 7.5 lists optimal values of k for various exponent sizes and compares the number of multiplication and

Exponent (bits) Optimal kWork at kWork with 7.1

squarings required against algorithm 7.1.

Figure 7.5: Optimal Values of k for k-ary Exponentiation

7.2.2 Sliding-Window Exponentiation

A simple modification to the previous algorithm is only generate the upper half of the table in the range $2^{k-1} \le g < 2^k$. Essentially this is a table for all values of g where the most significant bit of g is a one. However, in order for this to be allowed in the algorithm values of g in the range $0 \le g < 2^{k-1}$ must be avoided.

Table 7.6 lists optimal values of k for various exponent sizes and compares the work required against algorithm 7.4.

Exponent (bits)	Optimal k	Work at k	Work with 7.4
16	3	24	27
32	3	45	49
64	4	87	92
128	4	167	175
256	5	322	335
512	6	628	645
1024	6	1225	1257
2048	7	2403	2452
4096	8	4735	4808

Figure 7.6: Optimal Values of k for Sliding Window Exponentiation

```
Algorithm Sliding Window k-ary Exponentiation.

Input. Integer a, b, k and t

Output. c = a^b

1. c \leftarrow 1
2. for i from t - 1 to 0 do
2.1 If the i'th bit of b is a zero then
2.1.1 c \leftarrow c^2
2.2 else do
2.2.1 c \leftarrow c^{2^k}
2.2.2 Extract the k bits from (b_i b_{i-1} \dots b_{i-(k-1)}) and store it in g.
2.2.3 c \leftarrow c \cdot a^g
2.2.4 i \leftarrow i - k
3. Return c.
```

Figure 7.7: Sliding Window k-ary Exponentiation

Similar to the previous algorithm this algorithm must have a special handler when fewer than k bits are left in the exponent. While this algorithm requires the same number of squarings it can potentially have fewer multiplications. The pre-computed table a^g is also half the size as the previous table.

Consider the exponent $b=111101011001000_2\equiv 31432_{10}$ with k=3 using both algorithms. The first algorithm will divide the exponent up as the following five 3-bit words $b\equiv (111,101,011,001,000)_2$. The second algorithm will break the exponent as $b\equiv (111,101,0,110,0,100,0)_2$. The single digit 0 in the second representation are where a single squaring took place instead of a squaring and multiplication. In total the first method requires 10 multiplications and 18 squarings. The second method requires 8 multiplications and 18 squarings.

In general the sliding window method is never slower than the generic k-ary method and often it is slightly faster.

7.3 Modular Exponentiation

Modular exponentiation is essentially computing the power of a base within a finite field or ring. For example, computing $d \equiv a^b \pmod{c}$ is a modular exponentiation. Instead of first computing a^b and then reducing it modulo c the intermediate result is reduced modulo c after every squaring or multiplication operation.

This guarantees that any intermediate result is bounded by $0 \le d \le c^2 - 2c + 1$ and can be reduced modulo c quickly using one of the algorithms presented in chapter six.

Before the actual modular exponentiation algorithm can be written a wrapper algorithm must be written first. This algorithm will allow the exponent b to be negative which is computed as $c \equiv (1/a)^{|b|} \pmod{d}$. The value of $(1/a) \mod c$ is computed using the modular inverse (see ??). If no inverse exists the algorithm terminates with an error.

```
Algorithm mp_exptmod.

Input. mp_int a, b and c

Output. y \equiv g^x \pmod{p}

1. If c.sign = MP\_NEG return(MP\_VAL).

2. If b.sign = MP\_NEG then

2.1 g' \leftarrow g^{-1} \pmod{c}

2.2 x' \leftarrow |x|

2.3 Compute d \equiv g'^{x'} \pmod{c} via recursion.

3. if p is odd \mathbf{OR} p is a D.R. modulus then

3.1 Compute y \equiv g^x \pmod{p} via algorithm mp_exptmod_fast.

4. else

4.1 Compute y \equiv g^x \pmod{p} via algorithm s_mp_exptmod.
```

Figure 7.8: Algorithm mp_exptmod

Algorithm mp_exptmod. The first algorithm which actually performs modular exponentiation is algorithm s_mp_exptmod. It is a sliding window k-ary algorithm which uses Barrett reduction to reduce the product modulo p. The second algorithm mp_exptmod_fast performs the same operation except it uses either Montgomery or Diminished Radix reduction. The two latter reduction algorithms are clumped in the same exponentiation algorithm since their arguments are essentially the same (two mp_ints and one mp_digit).

```
File: bn_mp_exptmod.c

016

017

018  /* this is a shell function that calls either the normal or Montgomery

019  * exptmod functions. Originally the call to the montgomery code was

020  * embedded in the normal function but that wasted alot of stack space

021  * for nothing (since 99% of the time the Montgomery code would be called)
```

```
022
       */
023
      int mp_exptmod (mp_int * G, mp_int * X, mp_int * P, mp_int * Y)
024
025
        int dr;
026
027
        /* modulus P must be positive */
        if (P->sign == MP_NEG) {
028
           return MP_VAL;
029
030
031
032
        /* if exponent X is negative we have to recurse */
033
        if (X->sign == MP_NEG) {
034
           mp_int tmpG, tmpX;
035
           int err;
036
037
           /* first compute 1/G mod P */
           if ((err = mp_init(&tmpG)) != MP_OKAY) {
038
039
              return err;
040
           if ((err = mp_invmod(G, P, &tmpG)) != MP_OKAY) {
041
042
              mp_clear(&tmpG);
043
              return err;
044
045
046
           /* now get |X| */
047
           if ((err = mp_init(&tmpX)) != MP_OKAY) {
048
              mp_clear(&tmpG);
049
              return err;
050
051
           if ((err = mp_abs(X, &tmpX)) != MP_OKAY) {
052
              mp_clear_multi(&tmpG, &tmpX, NULL);
053
              return err;
054
055
           /* and now compute (1/G)**|X| instead of G**X[X < 0] */
056
           err = mp_exptmod(&tmpG, &tmpX, P, Y);
057
           mp_clear_multi(&tmpG, &tmpX, NULL);
058
059
           return err;
060
061
062
        /* is it a DR modulus? */
063
        dr = mp_dr_is_modulus(P);
```

```
064
065
        /* if not, is it a uDR modulus? */
        if (dr == 0) {
066
067
           dr = mp_reduce_is_2k(P) << 1;</pre>
068
069
        /* if the modulus is odd or dr != 0 use the fast method */
070
071
        if (mp_isodd (P) == 1 || dr != 0) {
072
          return mp_exptmod_fast (G, X, P, Y, dr);
073
        } else {
074
          /* otherwise use the generic Barrett reduction technique */
075
          return s_mp_exptmod (G, X, P, Y);
076
        }
      }
077
078
```

In order to keep the algorithms in a known state the first step on line 28 is to reject any negative modulus as input. If the exponent is negative the algorithm tries to perform a modular exponentiation with the modular inverse of the base G. The temporary variable tmpG is assigned the modular inverse of G and tmpX is assigned the absolute value of X. The algorithm will recuse with these new values with a positive exponent.

If the exponent is positive the algorithm resumes the exponentiation. Line 63 determines if the modulus is of the restricted Diminished Radix form. If it is not line 67 attempts to determine if it is of a unrestricted Diminished Radix form. The integer dr will take on one of three values.

- 1. dr = 0 means that the modulus is not of either restricted or unrestricted Diminished Radix form.
- 2. dr = 1 means that the modulus is of restricted Diminished Radix form.
- 3. dr = 2 means that the modulus is of unrestricted Diminished Radix form.

Line 70 determines if the fast modular exponentiation algorithm can be used. It is allowed if $dr \neq 0$ or if the modulus is odd. Otherwise, the slower s_mp_exptmod algorithm is used which uses Barrett reduction.

7.3.1 Barrett Modular Exponentiation

```
Algorithm s_mp_exptmod.
 Input. mp_int a, b and c
 Output. y \equiv g^x \pmod{p}
2. winsize \leftarrow \begin{cases} 2 & \text{if } k \le 7\\ 3 & \text{if } 7 < k \le 36\\ 4 & \text{if } 36 < k \le 140\\ 5 & \text{if } 140 < k \le 450\\ 6 & \text{if } 450 < k \le 1303\\ 7 & \text{if } 1303 < k \le 3529\\ 8 & \text{if } 3529 < k \end{cases}
3. Initialize 2^{winsize}
3. Initialize 2^{winsize} mp_ints in an array named M and one mp_int named \mu
4. Calculate the \mu required for Barrett Reduction (mp\_reduce\_setup).
5. M_1 \leftarrow g \pmod{p}
 Setup the table of small powers of g. First find g^{2^{winsize}} and then all multiples of it.
 6. k \leftarrow 2^{winsize-1}
 7. M_k \leftarrow M_1
 8. for ix from 0 to winsize - 2 do
    8.1 \ M_k \leftarrow (M_k)^2 \ (mp\_sqr)
8.2 M_k \leftarrow M_k \pmod{p} \pmod{p} (mp\_reduce)
9. for ix from 2^{winsize-1} + 1 to 2^{winsize} - 1 do
    9.1 \ M_{ix} \leftarrow M_{ix-1} \cdot M_1 \ (mp\_mul)
    9.2 \ M_{ix} \leftarrow M_{ix} \ (\text{mod } p) \ (\textit{mp\_reduce})
 10. res \leftarrow 1
 Start Sliding Window.
 11. mode \leftarrow 0, bitcnt \leftarrow 1, buf \leftarrow 0, digidx \leftarrow x.used - 1, bitcpy \leftarrow 0, bitbuf \leftarrow 0
 12. Loop
    12.1 \ bitcnt \leftarrow bitcnt - 1
    12.2 \text{ If } bitcnt = 0 \text{ then do}
        12.2.1 If digidx = -1 goto step 13.
        12.2.2 \ buf \leftarrow x_{digidx}
        12.2.3 \ digidx \leftarrow digidx - 1
        12.2.4 \ bitcnt \leftarrow lq(\beta)
 Continued on next page.
```

Figure 7.9: Algorithm s_mp_exptmod

```
Algorithm s_mp_exptmod (continued).
Input. mp_int a, b and c
Output. y \equiv g^x \pmod{p}
  12.3 \ y \leftarrow (buf >> (lg(\beta) - 1)) \ \text{AND } 1
  12.4\ buf \leftarrow buf << 1
  12.5 if mode = 0 and y = 0 then goto step 12.
  12.6 \text{ if } mode = 1 \text{ and } y = 0 \text{ then do}
     12.6.1 \ res \leftarrow res^2
     12.6.2 \ res \leftarrow res \ (\text{mod } p)
     12.6.3 Goto step 12.
  12.7\ bitcpy \leftarrow bitcpy + 1
  12.8 \ bitbuf \leftarrow bitbuf + (y << (winsize - bitcpy))
  12.9 \ mode \leftarrow 2
  12.10 \text{ If } bitcpy = winsize \text{ then do}
     Window is full so perform the squarings and single multiplication.
     12.10.1 for ix from 0 to winsize - 1 do
        12.10.1.1\ res \leftarrow res^2
        12.10.1.2 \ res \leftarrow res \ (\text{mod } p)
     12.10.2 \ res \leftarrow res \cdot M_{bitbuf}
     12.10.3 \ res \leftarrow res \pmod{p}
     Reset the window.
     12.10.4\ bitcpy \leftarrow 0, bitbuf \leftarrow 0, mode \leftarrow 1
No more windows left. Check for residual bits of exponent.
13. If mode = 2 and bitcpy > 0 then do
  13.1 for ix form 0 to bitcpy - 1 do
     13.1.1 \ res \leftarrow res^2
     13.1.2 \ res \leftarrow res \pmod{p}
     13.1.3\ bitbuf \leftarrow bitbuf << 1
     13.1.4 If bitbuf AND 2^{winsize} \neq 0 then do
        13.1.4.1 \ res \leftarrow res \cdot M_1
       13.1.4.2 \ res \leftarrow res \pmod{p}
14. y \leftarrow res
15. Clear res, mu and the M array.
16. Return(MP\_OKAY).
```

Figure 7.10: Algorithm s_mp_exptmod (continued)

Algorithm s_mp_exptmod. This algorithm computes the x'th power of g modulo p and stores the result in y. It takes advantage of the Barrett reduction

algorithm to keep the product small throughout the algorithm.

The first two steps determine the optimal window size based on the number of bits in the exponent. The larger the exponent the larger the window size becomes. After a window size winsize has been chosen an array of $2^{winsize}$ mp_int variables is allocated. This table will hold the values of $g^x \pmod{p}$ for $2^{winsize-1} < x < 2^{winsize}$.

After the table is allocated the first power of g is found. Since $g \geq p$ is allowed it must be first reduced modulo p to make the rest of the algorithm more efficient. The first element of the table at $2^{winsize-1}$ is found by squaring M_1 successively winsize-2 times. The rest of the table elements are found by multiplying the previous element by M_1 modulo p.

Now that the table is available the sliding window may begin. The following list describes the functions of all the variables in the window.

- 1. The variable *mode* dictates how the bits of the exponent are interpreted.
 - (a) When mode = 0 the bits are ignored since no non-zero bit of the exponent has been seen yet. For example, if the exponent were simply 1 then there would be $lg(\beta) 1$ zero bits before the first non-zero bit. In this case bits are ignored until a non-zero bit is found.
 - (b) When mode = 1 a non-zero bit has been seen before and a new winsize-bit window has not been formed yet. In this mode leading 0 bits are read and a single squaring is performed. If a non-zero bit is read a new window is created.
 - (c) When mode = 2 the algorithm is in the middle of forming a window and new bits are appended to the window from the most significant bit downwards.
- 2. The variable *bitcnt* indicates how many bits are left in the current digit of the exponent left to be read. When it reaches zero a new digit is fetched from the exponent.
- 3. The variable buf holds the currently read digit of the exponent.
- 4. The variable digidx is an index into the exponents digits. It starts at the leading digit x.used 1 and moves towards the trailing digit.
- 5. The variable *bitcpy* indicates how many bits are in the currently formed window. When it reaches *winsize* the window is flushed and the appropriate operations performed.

6. The variable bitbuf holds the current bits of the window being formed.

All of step 12 is the window processing loop. It will iterate while there are digits available form the exponent to read. The first step inside this loop is to extract a new digit if no more bits are available in the current digit. If there are no bits left a new digit is read and if there are no digits left than the loop terminates.

After a digit is made available step 12.3 will extract the most significant bit of the current digit and move all other bits in the digit upwards. In effect the digit is read from most significant bit to least significant bit and since the digits are read from leading to trailing edges the entire exponent is read from most significant bit to least significant bit.

At step 12.5 if the *mode* and currently extracted bit y are both zero the bit is ignored and the next bit is read. This prevents the algorithm from having to perform trivial squaring and reduction operations before the first non-zero bit is read. Step 12.6 and 12.7-10 handle the two cases of mode = 1 and mode = 2 respectively.




Figure 7.11: Sliding Window State Diagram

By step 13 there are no more digits left in the exponent. However, there may be partial bits in the window left. If mode = 2 then a Left-to-Right algorithm is used to process the remaining few bits.

File: bn_s_mp_exptmod.c

```
016
017
      #ifdef MP_LOW_MEM
018
         #define TAB_SIZE 32
019
      #else
020
         #define TAB_SIZE 256
      #endif
021
022
023
      int s_mp_exptmod (mp_int * G, mp_int * X, mp_int * P, mp_int * Y)
024
025
        mp_int M[TAB_SIZE], res, mu;
026
        mp_digit buf;
027
                err, bitbuf, bitcpy, bitcnt, mode, digidx, x, y, winsize;
        int
028
029
        /* find window size */
030
        x = mp_count_bits (X);
031
        if (x <= 7) {
032
          winsize = 2;
        } else if (x <= 36) {}
033
034
         winsize = 3;
        } else if (x <= 140) {
035
036
          winsize = 4;
037
        \} else if (x <= 450) {
038
          winsize = 5;
039
        \} else if (x <= 1303) {
040
         winsize = 6;
041
        } else if (x <= 3529) {
042
         winsize = 7;
043
        } else {
044
          winsize = 8;
045
046
047
      #ifdef MP_LOW_MEM
048
          if (winsize > 5) {
             winsize = 5;
049
050
051
      #endif
052
053
        /* init M array */
054
        /* init first cell */
055
        if ((err = mp_init(&M[1])) != MP_OKAY) {
056
           return err;
057
```

```
058
059
        /* now init the second half of the array */
060
        for (x = 1 << (winsize-1); x < (1 << winsize); x++) {
061
          if ((err = mp_init(&M[x])) != MP_OKAY) {
062
            for (y = 1 << (winsize-1); y < x; y++) {
063
              mp_clear (&M[y]);
064
065
            mp_clear(&M[1]);
066
            return err;
067
068
069
070
        /* create mu, used for Barrett reduction */
071
        if ((err = mp_init (&mu)) != MP_OKAY) {
072
          goto __M;
073
074
        if ((err = mp_reduce_setup (&mu, P)) != MP_OKAY) {
075
          goto __MU;
076
077
078
        /* create M table
079
080
         * The M table contains powers of the base,
081
         * e.g. M[x] = G**x \mod P
082
083
         * The first half of the table is not
084
         * computed though accept for M[0] and M[1]
085
086
        if ((err = mp_mod (G, P, &M[1])) != MP_OKAY) {
087
          goto __MU;
088
        }
089
090
        /* compute the value at M[1<<(winsize-1)] by squaring</pre>
091
         * M[1] (winsize-1) times
092
         */
093
        if ((err = mp_copy (&M[1], &M[1 << (winsize - 1)])) != MP_OKAY) {
094
          goto __MU;
095
096
097
        for (x = 0; x < (winsize - 1); x++) {
098
          if ((err = mp_sqr (&M[1 << (winsize - 1)],
                              &M[1 << (winsize - 1)])) != MP_OKAY) {
099
```

```
100
            goto __MU;
101
102
          if ((err = mp_reduce (&M[1 << (winsize - 1)], P, &mu)) != MP_OKAY) {
103
            goto __MU;
104
105
106
107
        /* create upper table, that is M[x] = M[x-1] * M[1] \pmod{P}
108
         * for x = (2**(winsize - 1) + 1) to (2**winsize - 1)
109
         */
        for (x = (1 << (winsize - 1)) + 1; x < (1 << winsize); x++) {
110
          if ((err = mp_mul (&M[x - 1], &M[1], &M[x])) != MP_OKAY) {
111
112
            goto __MU;
113
114
          if ((err = mp_reduce (&M[x], P, &mu)) != MP_OKAY) {
115
            goto __MU;
116
117
        }
118
119
        /* setup result */
        if ((err = mp_init (&res)) != MP_OKAY) {
120
121
          goto __MU;
122
123
        mp_set (&res, 1);
124
125
        /* set initial mode and bit cnt */
126
        mode
              = 0;
127
        bitcnt = 1;
128
        buf
               = 0;
129
        digidx = X->used - 1;
130
        bitcpy = 0;
        bitbuf = 0;
131
132
133
        for (;;) {
134
          /* grab next digit as required */
135
          if (--bitcnt == 0) {
            /* if digidx == -1 we are out of digits */
136
137
            if (digidx == -1) {
138
              break;
139
140
            /* read next digit and reset the bitcnt */
141
            buf
                   = X \rightarrow dp[digidx --];
```

```
142
            bitcnt = (int) DIGIT_BIT;
143
144
145
          /* grab the next msb from the exponent */
146
                = (buf >> (mp_digit)(DIGIT_BIT - 1)) & 1;
147
          buf <<= (mp_digit)1;</pre>
148
149
          /* if the bit is zero and mode == 0 then we ignore it
150
           * These represent the leading zero bits before the first 1 bit
151
           * in the exponent. Technically this opt is not required but it
           * does lower the # of trivial squaring/reductions used
152
153
           */
          if (mode == 0 \&\& y == 0) {
154
155
            continue;
156
          }
157
158
          /* if the bit is zero and mode == 1 then we square */
159
          if (mode == 1 && y == 0) {
160
            if ((err = mp_sqr (&res, &res)) != MP_OKAY) {
161
              goto __RES;
162
163
            if ((err = mp_reduce (&res, P, &mu)) != MP_OKAY) {
164
              goto __RES;
165
166
            continue;
          }
167
168
          /* else we add it to the window */
169
170
          bitbuf |= (y << (winsize - ++bitcpy));</pre>
171
          mode
                  = 2;
172
173
          if (bitcpy == winsize) {
174
            /* ok window is filled so square as required and multiply */
175
            /* square first */
176
            for (x = 0; x < winsize; x++) {
177
              if ((err = mp_sqr (&res, &res)) != MP_OKAY) {
178
                goto __RES;
179
              }
              if ((err = mp_reduce (&res, P, &mu)) != MP_OKAY) {
180
181
                goto __RES;
              }
182
183
```

```
184
185
            /* then multiply */
            if ((err = mp_mul (&res, &M[bitbuf], &res)) != MP_OKAY) {
186
187
              goto __RES;
188
            if ((err = mp_reduce (&res, P, &mu)) != MP_OKAY) {
189
190
              goto __RES;
191
192
            /* empty window and reset */
193
194
            bitcpy = 0;
195
            bitbuf = 0;
196
            mode = 1;
197
198
        }
199
200
        /* if bits remain then square/multiply */
201
        if (mode == 2 && bitcpy > 0) {
202
          /* square then multiply if the bit is set */
203
          for (x = 0; x < bitcpy; x++) {
            if ((err = mp_sqr (&res, &res)) != MP_OKAY) {
204
205
              goto __RES;
206
            if ((err = mp_reduce (&res, P, &mu)) != MP_OKAY) {
207
208
              goto __RES;
209
210
            bitbuf <<= 1;</pre>
211
212
            if ((bitbuf & (1 << winsize)) != 0) {
213
              /* then multiply */
              if ((err = mp_mul (&res, &M[1], &res)) != MP_OKAY) \{
214
215
                goto __RES;
216
217
              if ((err = mp_reduce (&res, P, &mu)) != MP_OKAY) {
218
                goto __RES;
219
220
          }
221
        }
222
223
224
        mp_exch (&res, Y);
225
        err = MP_OKAY;
```

```
226
      __RES:mp_clear (&res);
227
      __MU:mp_clear (&mu);
228
      __M:
229
        mp_clear(&M[1]);
        for (x = 1 << (winsize-1); x < (1 << winsize); x++) {
230
231
          mp_clear (&M[x]);
232
        }
233
        return err:
234
```

Lines 31 through 41 determine the optimal window size based on the length of the exponent in bits. The window divisions are sorted from smallest to greatest so that in each **if** statement only one condition must be tested. For example, by the **if** statement on line 33 the value of x is already known to be greater than 140.

The conditional piece of code beginning on line 47 allows the window size to be restricted to five bits. This logic is used to ensure the table of precomputed powers of G remains relatively small.

The for loop on line 60 initializes the M array while lines 61 and 74 compute the value of μ required for Barrett reduction.

- More later.

7.4 Quick Power of Two

Calculating $b = 2^a$ can be performed much quicker than with any of the previous algorithms. Recall that a logical shift left m << k is equivalent to $m \cdot 2^k$. By this logic when m = 1 a quick power of two can be achieved.

```
Algorithm mp_2expt.

Input. integer b
Output. a \leftarrow 2^b

1. a \leftarrow 0
2. If a.alloc < \lfloor b/lg(\beta) \rfloor + 1 then grow a appropriately.
3. a.used \leftarrow \lfloor b/lg(\beta) \rfloor + 1
4. a_{\lfloor b/lg(\beta) \rfloor} \leftarrow 1 << (b \bmod lg(\beta))
5. Return(MP\_OKAY).
```

Figure 7.12: Algorithm mp_2expt

Algorithm mp_2expt.

```
File: bn_mp_2expt.c
016
017
      /* computes a = 2**b
018
       * Simple algorithm which zeroes the int, grows it then just sets one bit
019
020
      * as required.
021
      */
022
023
      mp_2expt (mp_int * a, int b)
024
025
        int
               res;
026
027
       /* zero a as per default */
        mp_zero (a);
028
029
030
       /* grow a to accomodate the single bit */
        if ((res = mp_grow (a, b / DIGIT_BIT + 1)) != MP_OKAY) {
031
032
          return res;
033
034
035
        /* set the used count of where the bit will go */
036
        a->used = b / DIGIT_BIT + 1;
037
038
        /* put the single bit in its place */
039
       a->dp[b / DIGIT_BIT] = 1 << (b % DIGIT_BIT);
040
041
       return MP_OKAY;
042
```

Chapter 8

Higher Level Algorithms

This chapter discusses the various higher level algorithms that are required to complete a well rounded multiple precision integer package. These routines are less performance oriented than the algorithms of chapters five, six and seven but are no less important.

The first section describes a method of integer division with remainder that is universally well known. It provides the signed division logic for the package. The subsequent section discusses a set of algorithms which allow a single digit to be the 2nd operand for a variety of operations. These algorithms serve mostly to simplify other algorithms where small constants are required. The last two sections discuss how to manipulate various representations of integers. For example, converting from an mp_int to a string of character.

8.1 Integer Division with Remainder

Integer division aside from modular exponentiation is the most intensive algorithm to compute. Like addition, subtraction and multiplication the basis of this algorithm is the long-hand division algorithm taught to school children. Throughout this discussion several common variables will be used. Let x represent the divisor and y represent the dividend. Let q represent the integer quotient $\lfloor y/x \rfloor$ and let r represent the remainder $r = y - x \lfloor y/x \rfloor$. The following simple algorithm will be used to start the discussion.

```
Algorithm Radix-\beta Integer Division.

Input. integer x and y
Output. q = \lfloor y/x \rfloor, r = y - xq

1. q \leftarrow 0
2. n \leftarrow ||y|| - ||x||
3. for t from n down to 0 do
3.1 Maximize k such that kx\beta^t is less than or equal to y and (k+1)x\beta^t is greater.
3.2 q \leftarrow q + k\beta^t
3.3 y \leftarrow y - kx\beta^t
4. r \leftarrow y
5. Return(q, r)
```

Figure 8.1: Algorithm Radix- β Integer Division

As children we are taught this very simple algorithm for the case of $\beta=10$. Almost instinctively several optimizations are taught for which their reason of existing are never explained. For this example let y=5471 represent the dividend and x=23 represent the divisor.

To find the first digit of the quotient the value of k must be maximized such that $kx\beta^t$ is less than or equal to y and simultaneously $(k+1)x\beta^t$ is greater than y. Implicitly k is the maximum value the t'th digit of the quotient may have. The habitual method used to find the maximum is to "eyeball" the two numbers, typically only the leading digits and quickly estimate a quotient. By only using leading digits a much simpler division may be used to form an educated guess at what the value must be. In this case $k = \lfloor 54/23 \rfloor = 2$ quickly arises as a possible solution. Indeed $2x\beta^2 = 4600$ is less than y = 5471 and simultaneously $(k+1)x\beta^2 = 6900$ is larger than y. As a result $k\beta^2$ is added to the quotient which now equals q = 200 and 4600 is subtracted from y to give a remainder of y = 841.

Again this process is repeated to produce the quotient digit k=3 which makes the quotient $q=200+3\beta=230$ and the remainder $y=841-3x\beta=181$. Finally the last iteration of the loop produces k=7 which leads to the quotient q=230+7=237 and the remainder y=181-7x=20. The final quotient and remainder found are q=237 and r=y=20 which are indeed correct since $237 \cdot 23 + 20 = 5471$ is true.

8.1.1 Quotient Estimation

As alluded to earlier the quotient digit k can be estimated from only the leading digits of both the divisor and dividend. When p leading digits are used from both the divisor and dividend to form an estimation the accuracy of the estimation rises as p grows. Technically speaking the estimation is based on assuming the lower ||y|| - p and ||x|| - p lower digits of the dividend and divisor are zero.

The value of the estimation may off by a few values in either direction and in general is fairly correct. A simplification [1, pp. 271] of the estimation technique is to use t+1 digits of the dividend and t digits of the divisor, in particularly when t=1. The estimate using this technique is never too small. For the following proof let t=||y||-1 and s=||x||-1 represent the most significant digits of the dividend and divisor respectively.

Proof. The quotient $\hat{k} = \lfloor (y_t \beta + y_{t-1})/x_s \rfloor$ is greater than or equal to $k = \lfloor y/(x \cdot \beta^{||y||-||x||-1}) \rfloor$. The first obvious case is when $\hat{k} = \beta - 1$ in which case the proof is concluded since the real quotient cannot be larger. For all other cases $\hat{k} = \lfloor (y_t \beta + y_{t-1})/x_s \rfloor$ and $\hat{k}x_s \geq y_t \beta + y_{t-1} - x_s + 1$. The latter portion of the inequalility $-x_s + 1$ arises from the fact that a truncated integer division will give the same quotient for at most $x_s - 1$ values. Next a series of inequalities will prove the hypothesis.

$$y - \hat{k}x \le y - \hat{k}x_s \beta^s \tag{8.1}$$

This is trivially true since $x \geq x_s \beta^s$. Next we replace $\hat{k}x_s \beta^s$ by the previous inequality for $\hat{k}x_s$.

$$y - \hat{k}x \le y_t \beta^t + \dots + y_0 - (y_t \beta^t + y_{t-1} \beta^{t-1} - x_s \beta^t + \beta^s)$$
 (8.2)

By simplifying the previous inequality the following inequality is formed.

$$y - \hat{k}x \le y_{t-2}\beta^{t-2} + \dots + y_0 + x_s\beta^s - \beta^s$$
 (8.3)

Subsequently,

$$y_{t-2}\beta^{t-2} + \dots + y_0 + x_s\beta^s - \beta^s < x_s\beta^s \le x$$
 (8.4)

Which proves that $y - \hat{k}x \le x$ and by consequence $\hat{k} \ge k$ which concludes the proof. **QED**

8.1.2 Normalized Integers

For the purposes of division a normalized input is when the divisors leading digit x_n is greater than or equal to $\beta/2$. By multiplying both x and y by $j = \lfloor (\beta/2)/x_n \rfloor$ the quotient remains unchanged and the remainder is simply j times the original remainder. The purpose of normalization is to ensure the leading digit of the divisor is sufficiently large such that the estimated quotient will lie in the domain of a single digit. Consider the maximum dividend $(\beta-1) \cdot \beta + (\beta-1)$ and the minimum divisor $\beta/2$.

$$\frac{\beta^2 - 1}{\beta/2} \le 2\beta - \frac{2}{\beta} \tag{8.5}$$

At most the quotient approaches 2β , however, in practice this will not occur since that would imply the previous quotient digit was too small.

8.1.3 Radix- β Division with Remainder

209

```
Algorithm mp_div.
Input. mp_int a, b
Output. c = \lfloor a/b \rfloor, d = a - bc
1. If b = 0 \operatorname{return}(MP_{-}VAL).
2. If |a| < |b| then do
   2.1~d \leftarrow a
   2.2~c \leftarrow 0
   2.3 Return(MP\_OKAY).
Setup the quotient to receive the digits.
3. Grow q to a.used + 2 digits.
4. q \leftarrow 0
5. x \leftarrow |a|, y \leftarrow |b|
6. sign \leftarrow \begin{cases} MP\_ZPOS & \text{if } a.sign = b.sign \\ MP\_NEG & \text{otherwise} \end{cases}
Normalize the inputs such that the leading digit of y is greater than or equal to \beta/2.
7. norm \leftarrow (lg(\beta) - 1) - (\lceil lg(y) \rceil \pmod{lg(\beta)})
8. x \leftarrow x \cdot 2^{norm}, y \leftarrow y \cdot 2^{norm}
Find the leading digit of the quotient.
9. n \leftarrow x.used - 1, t \leftarrow y.used - 1
10. y \leftarrow y \cdot \beta^{n-t}
11. While (x \ge y) do
11.1 \ q_{n-t} \leftarrow q_{n-t} + 1
11.2 \ x \leftarrow x - y
12. \ y \leftarrow \lfloor y/\beta^{n-t} \rfloor
Continued on the next page.
```

Figure 8.2: Algorithm mp_div

```
Algorithm mp_div (continued).
Input. mp_int a, b
Output. c = |a/b|, d = a - bc
Now find the remainder fo the digits.
13. for i from n down to (t+1) do
   13.1 If i > x.used then jump to the next iteration of this loop.
   13.2 If x_i = y_t then
      13.2.1 \ q_{i-t-1} \leftarrow \beta - 1
   13.3 else
      13.3.1 \ \hat{r} \leftarrow x_i \cdot \beta + x_{i-1}
      13.3.2 \ \hat{r} \leftarrow |\hat{r}/y_t|
      13.3.3 \ q_{i-t-1} \leftarrow \hat{r}
   13.4 \ q_{i-t-1} \leftarrow q_{i-t-1} + 1
Fixup quotient estimation.
   13.5 Loop
      13.5.1 \ q_{i-t-1} \leftarrow q_{i-t-1} - 1
      13.5.2~t1 \leftarrow 0
      13.5.3 \ \text{t1}_0 \leftarrow y_{t-1}, \ \text{t1}_1 \leftarrow y_t, \ \text{t1.} used \leftarrow 2
      13.5.4 \ t1 \leftarrow t1 \cdot q_{i-t-1}
      13.5.5 \ \text{t2}_0 \leftarrow x_{i-2}, \ \text{t2}_1 \leftarrow x_{i-1}, \ \text{t2}_2 \leftarrow x_i, \ \text{t2.} used \leftarrow 3
      13.5.6 \text{ If } |t1| > |t2| \text{ then goto step } 13.5.
   13.6 \ \text{t1} \leftarrow y \cdot q_{i-t-1}
   13.7 t1 \leftarrow t1 \cdot \beta^{i-t-1}
   13.8 \ x \leftarrow x - \ \text{t1}
   13.9 If x.sign = MP\_NEG then
      13.10 \text{ t1} \leftarrow y
      13.11 t<br/>1 \leftarrow t<br/>1 · \beta^{i-t-1}
      13.12~x \leftarrow x + ~\text{t1}
      13.13 \ q_{i-t-1} \leftarrow q_{i-t-1} - 1
Finalize the result.
14. Clamp excess digits of q
15. c \leftarrow q, c.sign \leftarrow sign
16. x.sign \leftarrow a.sign
17. d \leftarrow \lfloor x/2^{norm} \rfloor
18. Return(MP\_OKAY).
```

Figure 8.3: Algorithm mp_div (continued)

Algorithm mp_div. This algorithm will calculate quotient and remainder from an integer division given a dividend and divisor. The algorithm is a signed division and will produce a fully qualified quotient and remainder.

First the divisor b must be non-zero which is enforced in step one. If the divisor is larger than the dividend than the quotient is implicitly zero and the remainder is the dividend.

After the first two trivial cases of inputs are handled the variable q is setup to receive the digits of the quotient. Two unsigned copies of the divisor y and dividend x are made as well. The core of the division algorithm is an unsigned division and will only work if the values are positive. Now the two values x and y must be normalized such that the leading digit of y is greater than or equal to $\beta/2$. This is performed by shifting both to the left by enough bits to get the desired normalization.

At this point the division algorithm can begin producing digits of the quotient. Recall that maximum value of the estimation used is $2\beta - \frac{2}{\beta}$ which means that a digit of the quotient must be first produced by another means. In this case y is shifted to the left $(step\ ten)$ so that it has the same number of digits as x. The loop on step eleven will subtract multiples of the shifted copy of y until x is smaller. Since the leading digit of y is greater than or equal to $\beta/2$ this loop will iterate at most two times to produce the desired leading digit of the quotient.

Now the remainder of the digits can be produced. The equation $\hat{q} = \lfloor \frac{x_i \beta + x_{i-1}}{y_t} \rfloor$ is used to fairly accurately approximate the true quotient digit. The estimation can in theory produce an estimation as high as $2\beta - \frac{2}{\beta}$ but by induction the upper quotient digit is correct (as established on step eleven) and the estimate must be less than β .

Recall from section 8.1.1 that the estimation is never too low but may be too high. The next step of the estimation process is to refine the estimation. The loop on step 13.5 uses $x_i\beta^2 + x_{i-1}\beta + x_{i-2}$ and $q_{i-t-1}(y_t\beta + y_{t-1})$ as a higher order approximation to adjust the quotient digit.

After both phases of estimation the quotient digit may still be off by a value of one¹. Steps 13.6 and 13.7 subtract the multiple of the divisor from the dividend (*Similar to step 3.3 of algorithm 8.1* and then subsequently add a multiple of the divisor if the quotient was too large.

Now that the quotient has been determine finializing the result is a matter of clamping the quotient, fixing the sizes and de-normalizing the remainder. An important aspect of this algorithm seemingly overlooked in other descriptions

¹This is similar to the error introduced by optimizing Barrett reduction.

such as that of Algorithm 14.20 HAC [2, pp. 598] is that when the estimations are being made (inside the loop on step 13.5) that the digits y_{t-1} , x_{i-2} and x_{i-1} may lie outside their respective boundaries. For example, if t=0 or $i \leq 1$ then the digits would be undefined. In those cases the digits should respectively be replaced with a zero.

```
File: bn_mp_div.c
016
017
      /* integer signed division.
018
       * c*b + d == a [e.g. a/b, c=quotient, d=remainder]
019
       * HAC pp.598 Algorithm 14.20
020
021
       * Note that the description in HAC is horribly
022
       * incomplete. For example, it doesn't consider
023
       * the case where digits are removed from 'x' in
024
       * the inner loop. It also doesn't consider the
025
       * case that y has fewer than three digits, etc..
026
027
       * The overall algorithm is as described as
028
       * 14.20 from HAC but fixed to treat these cases.
029
      */
030
      int mp_div (mp_int * a, mp_int * b, mp_int * c, mp_int * d)
031
032
        mp_int q, x, y, t1, t2;
033
                res, n, t, i, norm, neg;
        int
034
        /* is divisor zero ? */
035
        if (mp_iszero (b) == 1) {
036
037
          return MP_VAL;
038
039
        /* if a < b then q=0, r = a */
040
041
        if (mp\_cmp\_mag (a, b) == MP\_LT) {
042
          if (d != NULL) {
043
            res = mp_copy (a, d);
044
          } else {
            res = MP_OKAY;
045
046
          if (c != NULL) {
047
048
            mp_zero (c);
049
050
          return res;
```

```
051
        }
052
053
        if ((res = mp_init_size (&q, a->used + 2)) != MP_OKAY) {
054
          return res;
055
056
        q.used = a->used + 2;
057
058
        if ((res = mp_init (&t1)) != MP_OKAY) {
059
          goto __Q;
060
061
062
        if ((res = mp_init (&t2)) != MP_OKAY) {
063
          goto __T1;
064
065
066
        if ((res = mp_init_copy (&x, a)) != MP_OKAY) {
067
          goto __T2;
068
069
070
        if ((res = mp_init_copy (&y, b)) != MP_OKAY) {
071
          goto __X;
072
073
074
        /* fix the sign */
075
        neg = (a->sign == b->sign) ? MP_ZPOS : MP_NEG;
076
        x.sign = y.sign = MP_ZPOS;
077
078
        /* normalize both x and y, ensure that y >= b/2, [b == 2**DIGIT_BIT] */
079
        norm = mp_count_bits(&y) % DIGIT_BIT;
080
        if (norm < (int)(DIGIT_BIT-1)) {</pre>
081
           norm = (DIGIT_BIT-1) - norm;
082
           if ((res = mp_mul_2d (&x, norm, &x)) != MP_OKAY) {
083
             goto __Y;
084
085
           if ((res = mp_mul_2d (&y, norm, &y)) != MP_OKAY) {
086
             goto __Y;
087
088
        } else {
089
           norm = 0;
090
091
092
        /* note hac does 0 based, so if used==5 then its 0,1,2,3,4, e.g. use 4 */
```

```
093
        n = x.used - 1;
094
        t = y.used - 1;
095
096
        /* while (x >= y*b**n-t) do { q[n-t] += 1; x -= y*b**\{n-t\} } */
097
        if ((res = mp_lshd (&y, n - t)) != MP_OKAY) { /* y = y*b**\{n-t\} */
098
          goto __Y;
099
100
101
        while (mp_cmp (&x, &y) != MP_LT) {
102
          ++(q.dp[n - t]);
          if ((res = mp_sub (&x, &y, &x)) != MP_OKAY) {
103
104
            goto __Y;
          }
105
106
107
108
        /* reset y by shifting it back down */
109
        mp_rshd (&y, n - t);
110
111
        /* step 3. for i from n down to (t + 1) */
        for (i = n; i >= (t + 1); i--) {
112
          if (i > x.used) {
113
114
            continue;
115
116
          /* step 3.1 if xi == yt then set q\{i-t-1\} to b-1,
117
           * otherwise set q\{i-t-1\} to (xi*b + x\{i-1\})/yt */
118
          if (x.dp[i] == y.dp[t]) {
119
120
            q.dp[i - t - 1] = ((((mp_digit)1) << DIGIT_BIT) - 1);
121
          } else {
122
            mp_word tmp;
123
            tmp = ((mp_word) x.dp[i]) << ((mp_word) DIGIT_BIT);</pre>
124
            tmp |= ((mp_word) x.dp[i - 1]);
125
            tmp /= ((mp_word) y.dp[t]);
126
            if (tmp > (mp_word) MP_MASK)
127
              tmp = MP_MASK;
            q.dp[i - t - 1] = (mp\_digit) (tmp & (mp\_word) (MP\_MASK));
128
129
130
          /* while (q\{i-t-1\} * (yt * b + y\{t-1\})) >
131
                    xi * b**2 + xi-1 * b + xi-2
132
133
             do q\{i-t-1\} -= 1;
134
```

```
135
          */
136
          q.dp[i - t - 1] = (q.dp[i - t - 1] + 1) & MP_MASK;
137
138
            q.dp[i - t - 1] = (q.dp[i - t - 1] - 1) & MP_MASK;
139
140
            /* find left hand */
141
            mp_zero (&t1);
142
            t1.dp[0] = (t - 1 < 0) ? 0 : y.dp[t - 1];
143
            t1.dp[1] = y.dp[t];
144
            t1.used = 2;
            if ((res = mp_mul_d (&t1, q.dp[i - t - 1], &t1)) != MP_OKAY) {
145
146
              goto __Y;
147
148
149
            /* find right hand */
150
            t2.dp[0] = (i - 2 < 0) ? 0 : x.dp[i - 2];
151
            t2.dp[1] = (i - 1 < 0) ? 0 : x.dp[i - 1];
152
            t2.dp[2] = x.dp[i];
153
            t2.used = 3;
          } while (mp_cmp_mag(&t1, &t2) == MP_GT);
154
155
          /* step 3.3 x = x - q\{i-t-1\} * y * b**\{i-t-1\} */
156
          if ((res = mp_mul_d (&y, q.dp[i - t - 1], &t1)) != MP_OKAY) {
157
158
            goto __Y;
159
160
          if ((res = mp_lshd (&t1, i - t - 1)) != MP_OKAY) {
161
162
            goto __Y;
163
164
165
          if ((res = mp_sub (&x, &t1, &x)) != MP_OKAY) {
166
            goto __Y;
167
168
          /* if x < 0 then { x = x + y*b**\{i-t-1\}; q\{i-t-1\} -= 1; \} */
169
170
          if (x.sign == MP_NEG) {
171
            if ((res = mp_copy (&y, &t1)) != MP_OKAY) {
172
              goto __Y;
173
            if ((res = mp_lshd (&t1, i - t - 1)) != MP_OKAY) {
174
175
              goto __Y;
176
```

```
if ((res = mp_add (&x, &t1, &x)) != MP_OKAY) {
177
178
              goto __Y;
179
180
181
            q.dp[i - t - 1] = (q.dp[i - t - 1] - 1UL) & MP_MASK;
182
        }
183
184
185
        /* now q is the quotient and x is the remainder
186
         * [which we have to normalize]
         */
187
188
189
        /* get sign before writing to c */
190
        x.sign = a->sign;
191
192
        if (c != NULL) {
193
          mp_clamp (&q);
194
          mp_exch (&q, c);
195
          c->sign = neg;
196
197
198
        if (d != NULL) {
199
          mp_div_2d (&x, norm, &x, NULL);
200
          mp_exch (&x, d);
201
202
203
        res = MP_OKAY;
204
205
      __Y:mp_clear (&y);
206
      __X:mp_clear (&x);
207
      __T2:mp_clear (&t2);
      __T1:mp_clear (&t1);
208
209
      __Q:mp_clear (&q);
210
        return res;
211
```

The implementation of this algorithm differs slightly from the pseudo code presented previously. In this algorithm either of the quotient c or remainder d may be passed as a **NULL** pointer which indicates their value is not desired. For example, the C code to call the division algorithm with only the quotient is

```
mp_div(&a, &b, &c, NULL); /* c = [a/b] */
```

Lines 36 and 42 handle the two trivial cases of inputs which are division by zero and dividend smaller than the divisor respectively. After the two trivial cases all of the temporary variables are initialized. Line 75 determines the sign of the quotient and line 76 ensures that both x and y are positive.

The number of bits in the leading digit is calculated on line 80. Implictly an mp_int with r digits will require $lg(\beta)(r-1) + k$ bits of precision which when reduced modulo $lg(\beta)$ produces the value of k. In this case k is the number of bits in the leading digit which is exactly what is required. For the algorithm to operate k must equal $lg(\beta) - 1$ and when it does not the inputs must be normalized by shifting them to the left by $lg(\beta) - 1 - k$ bits.

Throughout the variables n and t will represent the highest digit of x and y respectively. These are first used to produce the leading digit of the quotient. The loop beginning on line 112 will produce the remainder of the quotient digits.

The conditional "continue" on line 113 is used to prevent the algorithm from reading past the leading edge of x which can occur when the algorithm eliminates multiple non-zero digits in a single iteration. This ensures that x_i is always non-zero since by definition the digits above the i'th position x must be zero in order for the quotient to be precise².

Lines 142, 143 and 150 through 152 manually construct the high accuracy estimations by setting the digits of the two mp_int variables directly.

8.2 Single Digit Helpers

This section briefly describes a series of single digit helper algorithms which come in handy when working with small constants. All of the helper functions assume the single digit input is positive and will treat them as such.

8.2.1 Single Digit Addition and Subtraction

Both addition and subtraction are performed by "cheating" and using mp_set followed by the higher level addition or subtraction algorithms. As a result these algorithms are subtantially simpler with a slight cost in performance.

²Precise as far as integer division is concerned.

```
Algorithm mp_add_d.
Input. mp_int a and a mp_digit b
Output. c = a + b

1. t \leftarrow b \ (mp\_set)
2. c \leftarrow a + t
3. Return(MP\_OKAY)
```

Figure 8.4: Algorithm mp_add_d

Algorithm mp_add_d. This algorithm initiates a temporary mp_int with the value of the single digit and uses algorithm mp_add to add the two values together.

```
File: bn_mp_add_d.c
016
017
      /* single digit addition */
018
019
      mp_add_d (mp_int * a, mp_digit b, mp_int * c)
020
021
                res, ix, oldused;
022
        mp_digit *tmpa, *tmpc, mu;
023
024
        /* grow c as required */
025
        if (c->alloc < a->used + 1) {
026
           if ((res = mp_grow(c, a->used + 1)) != MP_OKAY) {
027
              return res;
028
029
        }
030
        /* if a is negative and |a| >= b, call c = |a| - b */
031
032
        if (a->sign == MP_NEG \&\& (a->used > 1 || a->dp[0] >= b)) {
033
           /* temporarily fix sign of a */
034
           a->sign = MP_ZPOS;
035
           /* c = |a| - b */
036
037
           res = mp_sub_d(a, b, c);
038
           /* fix sign */
039
040
           a->sign = c->sign = MP_NEG;
041
042
           return res;
```

```
043
        }
044
045
        /* old number of used digits in c */
046
        oldused = c->used;
047
048
        /* sign always positive */
049
        c->sign = MP_ZPOS;
050
051
        /* source alias */
052
        tmpa
                = a->dp;
053
054
        /* destination alias */
055
               = c->dp;
        tmpc
056
057
        /* if a is positive */
058
        if (a->sign == MP_ZPOS) {
059
           /* add digit, after this we're propagating
060
            * the carry.
            */
061
062
                   = *tmpa++ + b;
           *tmpc
063
                   = *tmpc >> DIGIT_BIT;
064
           *tmpc++ &= MP_MASK;
065
066
           /* now handle rest of the digits */
067
           for (ix = 1; ix < a->used; ix++) \{
068
              *tmpc = *tmpa++ + mu;
069
                      = *tmpc >> DIGIT_BIT;
070
              *tmpc++ &= MP_MASK;
071
072
           /* set final carry */
073
           ix++;
074
           *tmpc++ = mu;
075
076
           /* setup size */
077
           c->used = a->used + 1;
        } else {
078
079
           /* a was negative and |a| < b */</pre>
080
           c->used = 1;
081
082
           /* the result is a single digit */
083
           if (a->used == 1) {
              *tmpc++ = b - a->dp[0];
084
```

```
085
            } else {
086
               *tmpc++
087
088
089
           /* setup count so the clearing of oldused
090
             * can fall through correctly
091
             */
092
           ix
                     = 1;
        }
093
094
        /* now zero to oldused */
095
        while (ix++ < oldused) {
096
097
           *tmpc++ = 0;
098
099
        mp_clamp(c);
100
101
        return MP_OKAY;
102
      }
103
```

Clever use of the letter 't'.

Subtraction

The single digit subtraction algorithm mp_sub_d is essentially the same except it uses mp_sub to subtract the digit from the mp_int.

8.2.2 Single Digit Multiplication

Single digit multiplication arises enough in division and radix conversion that it ought to be implement as a special case of the baseline multiplication algorithm. Essentially this algorithm is a modified version of algorithm s_mp_mul_digs where one of the multiplicands only has one digit.

Algorithm mp_mul_d. This algorithm quickly multiplies an mp_int by a small single digit value. It is specially tailored to the job and has a minimal of overhead. Unlike the full multiplication algorithms this algorithm does not require any significant temporary storage or memory allocations.

```
File: bn_mp_mul_d.c
016
017  /* multiply by a digit */
018  int
```

```
Algorithm mp_mul_d.

Input. mp_int a and a mp_digit b

Output. c = ab
```

```
1. pa \leftarrow a.used
2. Grow c to at least pa + 1 digits.
3. oldused \leftarrow c.used
4. c.used \leftarrow pa + 1
5. c.sign \leftarrow a.sign
6. \mu \leftarrow 0
7. for ix from 0 to pa - 1 do
7.1 \hat{r} \leftarrow \mu + a_{ix}b
7.2 c_{ix} \leftarrow \hat{r} \pmod{\beta}
7.3 \mu \leftarrow \lfloor \hat{r}/\beta \rfloor
8. c_{pa} \leftarrow \mu
9. for ix from pa + 1 to oldused do
9.1 c_{ix} \leftarrow 0
10. Clamp excess digits of c.
11. Return(MP\_OKAY).
```

Figure 8.5: Algorithm mp_mul_d

```
mp_mul_d (mp_int * a, mp_digit b, mp_int * c)
019
020
021
        mp_digit u, *tmpa, *tmpc;
022
        mp_word r;
023
        int
                 ix, res, olduse;
024
025
        /* make sure c is big enough to hold a*b */
026
        if (c->alloc < a->used + 1) {
027
          if ((res = mp_grow (c, a->used + 1)) != MP_OKAY) {
028
            return res;
029
        }
030
031
032
        /* get the original destinations used count */
033
        olduse = c->used;
034
035
        /* set the sign */
036
        c->sign = a->sign;
```

```
037
038
        /* alias for a->dp [source] */
039
        tmpa = a->dp;
040
041
        /* alias for c->dp [dest] */
042
        tmpc = c->dp;
043
044
        /* zero carry */
045
        u = 0;
046
047
        /* compute columns */
048
        for (ix = 0; ix < a->used; ix++) \{
          /* compute product and carry sum for this term */
049
                  = ((mp_word) u) + ((mp_word)*tmpa++) * ((mp_word)b);
050
051
052
          /* mask off higher bits to get a single digit */
053
          *tmpc++ = (mp_digit) (r & ((mp_word) MP_MASK));
054
055
          /* send carry into next iteration */
056
                  = (mp_digit) (r >> ((mp_word) DIGIT_BIT));
057
058
059
        /* store final carry [if any] */
        *tmpc++ = u;
060
061
062
        /* now zero digits above the top */
063
        while (ix++ < olduse) {
064
           *tmpc++ = 0;
065
066
067
        /* set used count */
068
        c->used = a->used + 1;
069
        mp_clamp(c);
070
071
        return MP_OKAY;
072
      }
```

In this implementation the destination c may point to the same mp_int as the source a since the result is written after the digit is read from the source. This function uses pointer aliases tmpa and tmpc for the digits of a and c respectively.

223

8.2.3 Single Digit Division

Like the single digit multiplication algorithm, single digit division is also a fairly common algorithm used in radix conversion. Since the divisor is only a single digit a specialized variant of the division algorithm can be used to compute the quotient.

```
Algorithm mp_div_d.
Input. mp_int a and a mp_digit b
Output. c = |a/b|, d = a - cb
1. If b = 0 then return(MP_{-}VAL).
2. If b = 3 then use algorithm mp_div_3 instead.
3. Init q to a.used digits.
4. \ q.used \leftarrow a.used
5. q.sign \leftarrow a.sign
6. \hat{w} \leftarrow 0
7. for ix from a.used - 1 down to 0 do
  7.1 \ \hat{w} \leftarrow \hat{w}\beta + a_{ix}
  7.2 If \hat{w} > b then
     7.2.1 t \leftarrow \lfloor \hat{w}/b \rfloor
     7.2.2 \ \hat{w} \leftarrow \hat{w} \pmod{b}
  7.3 else
     7.3.1 \ t \leftarrow 0
  7.4 \ q_{ix} \leftarrow t
8. d \leftarrow \hat{w}
9. Clamp excess digits of q.
10. c \leftarrow q
11. Return(MP_{-}OKAY).
```

Figure 8.6: Algorithm mp_div_d

Algorithm mp_div_d. This algorithm divides the mp_int a by the single mp_digit b using an optimized approach. Essentially in every iteration of the algorithm another digit of the dividend is reduced and another digit of quotient produced. Provided $b < \beta$ the value of \hat{w} after step 7.1 will be limited such that $0 \le \lfloor \hat{w}/b \rfloor < \beta$.

If the divisor b is equal to three a variant of this algorithm is used which is called mp_div_3. It replaces the division by three with a multiplication by $\lfloor \beta/3 \rfloor$ and the appropriate shift and residual fixup. In essence it is much like the Barrett reduction from chapter seven.

```
File: bn_mp_div_d.c
016
017    static int s_is_power_of_two(mp_digit b, int *p)
018    {
019        int x;
020
```

```
021
         for (x = 1; x < DIGIT_BIT; x++) {
022
            if (b == (((mp_digit)1)<<x)) {</pre>
023
                *p = x;
024
                return 1;
025
026
027
         return 0;
028
      }
029
030
      /* single digit division (based on routine from MPI) */
031
      int mp_div_d (mp_int * a, mp_digit b, mp_int * c, mp_digit * d)
032
      {
033
        mp_int q;
034
        mp_word w;
035
        mp_digit t;
036
        int
                res, ix;
037
038
        /* cannot divide by zero */
039
        if (b == 0) {
040
           return MP_VAL;
041
        }
042
043
        /* quick outs */
044
        if (b == 1 || mp_iszero(a) == 1) {
045
           if (d != NULL) {
046
               *d = 0;
047
048
           if (c != NULL) {
049
              return mp_copy(a, c);
050
051
           return MP_OKAY;
052
        }
053
054
        /* power of two ? */
055
        if (s_is_power_of_two(b, \&ix) == 1) {
056
           if (d != NULL) {
057
               *d = a \rightarrow dp[0] & ((1 << ix) - 1);
058
           }
059
           if (c != NULL) {
060
              return mp_div_2d(a, ix, c, NULL);
061
           }
062
           return MP_OKAY;
```

```
}
063
064
065
        /* three? */
066
        if (b == 3) {
067
           return mp_div_3(a, c, d);
068
069
070
        /* no easy answer [c'est la vie]. Just division */
        if ((res = mp_init_size(&q, a->used)) != MP_OKAY) {
071
072
           return res;
073
074
075
        q.used = a->used;
076
        q.sign = a->sign;
077
        w = 0;
078
        for (ix = a->used - 1; ix >= 0; ix--) {
079
           w = (w << ((mp_word)DIGIT_BIT)) | ((mp_word)a->dp[ix]);
080
           if (w >= b) {
081
              t = (mp\_digit)(w / b);
082
              w -= ((mp_word)t) * ((mp_word)b);
083
084
            } else {
              t = 0;
085
086
087
            q.dp[ix] = (mp_digit)t;
        }
088
089
090
        if (d != NULL) {
091
           *d = (mp_digit)w;
092
093
094
        if (c != NULL) {
095
           mp_clamp(&q);
096
           mp_exch(&q, c);
097
098
        mp_clear(&q);
099
100
        return res;
      }
101
102
```

Like the implementation of algorithm mp-div this algorithm allows either

of the quotient or remainder to be passed as a **NULL** pointer to indicate the respective value is not required. This allows a trivial single digit modular reduction algorithm, mp_mod_d to be created.

The division and remainder on lines 43 and @45,processors can divide a 64-bit quantity by a 32-bit quantity and produce the quotient and remainder simultaneously. Unfortunately the GCC compiler does not recognize that optimization and will actually produce two function calls to find the quotient and remainder respectively.

8.2.4 Single Digit Root Extraction

Finding the n'th root of an integer is fairly easy as far as numerical analysis is concerned. Algorithms such as the Newton-Raphson approximation (8.6) series will converge very quickly to a root for any continuous function f(x).

$$x_{i+1} = x_i - \frac{f(x_i)}{f'(x_i)} \tag{8.6}$$

In this case the n'th root is desired and $f(x) = x^n - a$ where a is the integer of which the root is desired. The derivative of f(x) is simply $f'(x) = nx^{n-1}$. Of particular importance is that this algorithm will be used over the integers not over the a more continuous domain such as the real numbers. As a result the root found can be above the true root by few and must be manually adjusted. Ideally at the end of the algorithm the n'th root b of an integer a is desired such that $b^n \leq a$.

```
Algorithm mp_n_root.
Input. mp_int a and a mp_digit b
Output. c^b \leq a
1. If b is even and a.sign = MP\_NEG \text{ return}(MP\_VAL).
2. \ sign \leftarrow a.sign
3. a.sign \leftarrow MP\_ZPOS
4. t2 \leftarrow 2
5. Loop
   5.1~\mathrm{t1} \leftarrow \mathrm{t2}
   5.2 \text{ t3} \leftarrow \text{t1}^{b-1}
   5.3 \text{ t2} \leftarrow \text{t3} \cdot \text{t1}
   5.4 \text{ t2} \leftarrow \text{t2} - a
   5.5 \text{ t3} \leftarrow \text{t3} \cdot b
   5.6 \text{ t3} \leftarrow |\text{t2/t3}|
   5.7 \text{ t2} \leftarrow \text{t1} - \text{t3}
   5.8 If t1 \neq t2 then goto step 5.
6. Loop
   6.1 \text{ t2} \leftarrow \text{t1}^b
   6.2 \text{ If } t2 > a \text{ then}
      6.2.1 \ \text{t1} \leftarrow \text{t1} - 1
      6.2.2 Goto step 6.
7. a.sign \leftarrow sign
8. c \leftarrow t1
9. c.sign \leftarrow sign
10. Return(MP\_OKAY).
```

Figure 8.7: Algorithm mp_n_root

Algorithm mp_n_root. This algorithm finds the integer n'th root of an input using the Newton-Raphson approach. It is partially optimized based on the observation that the numerator of $\frac{f(x)}{f'(x)}$ can be derived from a partial denominator. That is at first the denominator is calculated by finding x^{b-1} . This value can then be multiplied by x and have a subtracted from it to find the numerator. This saves a total of b-1 multiplications by t1 inside the loop.

The initial value of the approximation is t2 = 2 which allows the algorithm to start with very small values and quickly converge on the root. Ideally this algorithm is meant to find the n'th root of an input where n is bounded by $2 \le n \le 5$.

```
File: bn_mp_n_root.c
016
017
      /* find the n'th root of an integer
018
019
       * Result found such that (c)**b \le a and (c+1)**b > a
020
021
       * This algorithm uses Newton's approximation
022
       * x[i+1] = x[i] - f(x[i])/f'(x[i])
023
       * which will find the root in log(N) time where
024
       * each step involves a fair bit. This is not meant to
025
       * find huge roots [square and cube, etc].
026
027
      int mp_n_root (mp_int * a, mp_digit b, mp_int * c)
028
029
        mp_int t1, t2, t3;
030
        int
                res, neg;
031
032
        /* input must be positive if b is even */
033
        if ((b & 1) == 0 && a->sign == MP_NEG) {
034
          return MP_VAL;
035
036
037
        if ((res = mp_init (&t1)) != MP_OKAY) {
038
          return res;
039
        }
040
041
        if ((res = mp_init (&t2)) != MP_OKAY) {
042
          goto __T1;
043
        }
044
045
        if ((res = mp_init (&t3)) != MP_OKAY) {
046
          goto __T2;
047
048
049
        /* if a is negative fudge the sign but keep track */
050
                = a->sign;
051
        a->sign = MP_ZPOS;
052
053
        /* t2 = 2 */
054
        mp_set (&t2, 2);
055
056
        do {
```

```
/* t1 = t2 */
057
058
          if ((res = mp_copy (&t2, &t1)) != MP_OKAY) {
059
            goto __T3;
060
061
          /* t2 = t1 - ((t1**b - a) / (b * t1**(b-1))) */
062
063
064
          /* t3 = t1**(b-1) */
          if ((res = mp_expt_d (&t1, b - 1, &t3)) != MP_OKAY) {
065
066
            goto __T3;
067
068
069
          /* numerator */
          /* t2 = t1**b */
070
071
          if ((res = mp_mul (&t3, &t1, &t2)) != MP_OKAY) {
072
            goto __T3;
073
074
075
          /* t2 = t1**b - a */
          if ((res = mp_sub (&t2, a, &t2)) != MP_OKAY) {
076
077
            goto __T3;
078
          }
079
          /* denominator */
080
          /* t3 = t1**(b-1) * b */
081
          if ((res = mp_mul_d (&t3, b, &t3)) != MP_OKAY) {
082
083
            goto __T3;
084
          }
085
086
          /* t3 = (t1**b - a)/(b * t1**(b-1)) */
087
          if ((res = mp_div (&t2, &t3, &t3, NULL)) != MP_OKAY) {
088
            goto __T3;
089
090
091
          if ((res = mp_sub (&t1, &t3, &t2)) != MP_OKAY) {
092
            goto __T3;
093
        } while (mp_cmp (&t1, &t2) != MP_EQ);
094
095
096
        /* result can be off by a few so check */
097
        for (;;) {
098
          if ((res = mp_expt_d (&t1, b, &t2)) != MP_OKAY) {
```

```
099
            goto __T3;
100
101
          if (mp\_cmp (\&t2, a) == MP\_GT) {
102
103
             if ((res = mp_sub_d (&t1, 1, &t1)) != MP_OKAY) {
104
          goto __T3;
105
             }
          } else {
106
107
            break;
108
109
110
        /* reset the sign of a first */
111
112
        a->sign = neg;
113
114
        /* set the result */
115
        mp_exch (&t1, c);
116
117
        /* set the sign of the result */
118
        c->sign = neg;
119
120
        res = MP_OKAY;
121
122
      __T3:mp_clear (&t3);
123
      __T2:mp_clear (&t2);
124
      __T1:mp_clear (&t1);
125
        return res;
126
```

8.3 Random Number Generation

Random numbers come up in a variety of activities from public key cryptography to simple simulations and various randomized algorithms. Pollard-Rho factoring for example, can make use of random values as starting points to find factors of a composite integer. In this case the algorithm presented is solely for simulations and not intended for cryptographic use.

```
Algorithm mp_rand.
Input. An integer b
Output. A pseudo-random number of b digits

1. a \leftarrow 0
2. If b \le 0 return(MP\_OKAY)
3. Pick a non-zero random digit d.
4. a \leftarrow a + d
5. for ix from 1 to d - 1 do
5.1 a \leftarrow a \cdot \beta
5.2 Pick a random digit d.
5.3 a \leftarrow a + d
6. Return(MP\_OKAY).
```

Figure 8.8: Algorithm mp_rand

Algorithm mp_rand. This algorithm produces a pseudo-random integer of b digits. By ensuring that the first digit is non-zero the algorithm also guarantees that the final result has at least b digits. It relies heavily on a third-part random number generator which should ideally generate uniformly all of the integers from 0 to $\beta-1$.

```
File: bn_mp_rand.c
016
017
      /* makes a pseudo-random int of a given size */
018
      mp_rand (mp_int * a, int digits)
019
020
021
        int
                res;
022
        mp_digit d;
023
024
        mp_zero (a);
025
        if (digits <= 0) {
026
          return MP_OKAY;
027
028
029
        /* first place a random non-zero digit */
030
        do {
          d = ((mp_digit) abs (rand ()));
031
032
        } while (d == 0);
033
```

```
if ((res = mp_add_d (a, d, a)) != MP_OKAY) {
034
035
          return res;
036
037
038
        while (digits-- > 0) {
          if ((res = mp_lshd (a, 1)) != MP_OKAY) {
039
040
            return res;
041
042
          if ((res = mp_add_d (a, ((mp_digit) abs (rand ())), a)) != MP_OKAY) {
043
044
            return res;
045
046
        }
047
048
        return MP_OKAY;
049
```

8.4 Formatted Representations

The ability to emit a radix-n textual representation of an integer is useful for interacting with human parties. For example, the ability to be given a string of characters such as "114585" and turn it into the radix- β equivalent would make it easier to enter numbers into a program.

8.4.1 Reading Radix-n Input

For the purposes of this text we will assume that a simple lower ASCII map (8.9) is used for the values of from 0 to 63 to printable characters. For example, when the character "N" is read it represents the integer 23. The first 16 characters of the map are for the common representations up to hexadecimal. After that they match the "base64" encoding scheme which are suitable chosen such that they are printable. While outputting as base64 may not be too helpful for human operators it does allow communication via non binary mediums.

Value	Char	Value	Char	Value	Char	Value	Char
0	0	1	1	2	2	3	3
4	4	5	5	6	6	7	7
8	8	9	9	10	A	11	В
12	$^{\mathrm{C}}$	13	D	14	\mathbf{E}	15	\mathbf{F}
16	G	17	Η	18	I	19	J
20	K	21	L	22	${f M}$	23	N
24	O	25	P	26	Q	27	\mathbf{R}
28	\mathbf{S}	29	${ m T}$	30	U	31	V
32	W	33	X	34	Y	35	\mathbf{Z}
36	a	37	b	38	$^{\mathrm{c}}$	39	d
40	e	41	\mathbf{f}	42	g	43	h
44	i	45	j	46	k	47	1
48	\mathbf{m}	49	\mathbf{n}	50	O	51	p
52	\mathbf{q}	53	r	54	\mathbf{s}	55	\mathbf{t}
56	u	57	\mathbf{v}	58	w	59	X
60	У	61	${f z}$	62	+	63	/

Figure 8.9: Lower ASCII Map

```
Algorithm mp_read_radix.

Input. A string str of length sn and radix r.

Output. The radix-\beta equivalent mp_int.
```

```
1. If r < 2 or r > 64 return(MP\_VAL).

2. ix \leftarrow 0

3. If str_0 = "-" then do

3.1 ix \leftarrow ix + 1

3.2 sign \leftarrow MP\_NEG

4. else

4.1 sign \leftarrow MP\_ZPOS

5. a \leftarrow 0

6. for iy from ix to sn - 1 do

6.1 Let y denote the position in the map of str_{iy}.

6.2 If str_{iy} is not in the map or y \ge r then goto step 7.

6.3 a \leftarrow a \cdot r

6.4 a \leftarrow a + y

7. If a \ne 0 then a.sign \leftarrow sign

8. Return(MP\_OKAY).
```

Figure 8.10: Algorithm mp_read_radix

Algorithm mp_read_radix. This algorithm will read an ASCII string and produce the radix- β mp_int representation of the same integer. A minus symbol "-" may precede the string to indicate the value is negative, otherwise it is assumed to be positive. The algorithm will read up to sn characters from the input and will stop when it reads a character it cannot map the algorithm stops reading characters from the string. This allows numbers to be embedded as part of larger input without any significant problem.

```
File: bn_mp_read_radix.c
016
017
      /* read a string [ASCII] in a given radix */
018
      int mp_read_radix (mp_int * a, char *str, int radix)
019
020
        int
                 y, res, neg;
021
        char
                 ch:
022
023
        /* make sure the radix is ok */
        if (radix < 2 || radix > 64) {
024
025
          return MP_VAL;
```

```
026
        }
027
028
        /* if the leading digit is a
029
         * minus set the sign to negative.
030
         */
        if (*str == '-') {
031
032
          ++str;
033
          neg = MP_NEG;
034
        } else {
035
          neg = MP_ZPOS;
036
037
038
        /* set the integer to the default of zero */
039
        mp_zero (a);
040
041
        /* process each digit of the string */
042
        while (*str) {
043
          /* if the radix < 36 the conversion is case insensitive</pre>
044
           * this allows numbers like 1AB and 1ab to represent the same value
045
           * [e.g. in hex]
046
           */
047
          ch = (char) ((radix < 36) ? toupper (*str) : *str);</pre>
          for (y = 0; y < 64; y++) {
048
049
            if (ch == mp_s_rmap[y]) {
050
               break;
051
052
          }
053
054
          /* if the char was found in the map
055
           * and is less than the given radix add it
056
           * to the number, otherwise exit the loop.
057
           */
058
          if (y < radix) {
059
            if ((res = mp_mul_d (a, (mp_digit) radix, a)) != MP_OKAY) {
060
               return res;
061
            if ((res = mp_add_d (a, (mp_digit) y, a)) != MP_OKAY) {
062
063
               return res;
            }
064
065
          } else {
066
            break;
067
```

8.4.2 Generating Radix-n Output

Generating radix-n output is fairly trivial with a division and remainder algorithm.

```
Algorithm \mathbf{mp\_toradix}.

Input. A mp_int a and an integer r

Output. The radix-r representation of a
```

```
1. If r < 2 or r > 64 return(MP_-VAL).
2. If a = 0 then str = "0" and return(MP\_OKAY).
3. t \leftarrow a
4. str \leftarrow ""
5. if t.sign = MP\_NEG then
  5.1 \ str \leftarrow str + "-"
  5.2 \ t.sign = MP\_ZPOS
6. While (t \neq 0) do
  6.1 \ d \leftarrow t \pmod{r}
  6.2 \ t \leftarrow |t/r|
  6.3 Look up d in the map and store the equivalent character in y.
  6.4 \ str \leftarrow str + y
7. If str_0 = "-" then
  7.1 Reverse the digits str_1, str_2, \dots str_n.
8. Otherwise
  8.1 Reverse the digits str_0, str_1, \dots str_n.
9. Return(MP_{-}OKAY).
```

Figure 8.11: Algorithm mp_toradix

Algorithm mp_toradix. This algorithm computes the radix-r representation of an mp_int a. The "digits" of the representation are extracted by reducing successive powers of $\lfloor a/r^k \rfloor$ the input modulo r until $r^k > a$. Note that instead of actually dividing by r^k in each iteration the quotient $\lfloor a/r \rfloor$ is saved for the next iteration. As a result a series of trivial $n \times 1$ divisions are required instead of a series of $n \times k$ divisions. One design flaw of this approach is that the digits are produced in the reverse order (see 8.12). To remedy this flaw the digits must be swapped or simply "reversed".

```
File: bn_mp_toradix.c
016
017    /* stores a bignum as a ASCII string in a given radix (2..64) */
018    int mp_toradix (mp_int * a, char *str, int radix)
019    {
020        int        res, digs;
021        mp_int    t;
022        mp_digit d;
```

Value of a	Value of d	Value of str
1234	_	_
123	4	"4"
12	3	"43"
1	2	"432"
0	1	"4321"

Figure 8.12: Example of Algorithm mp_toradix.

```
023
        char
               *_s = str;
024
025
        /* check range of the radix */
026
        if (radix < 2 || radix > 64) {
027
          return MP_VAL;
028
029
030
        /* quick out if its zero */
031
        if (mp_iszero(a) == 1) {
           *str++ = '0';
032
           *str = '\0';
033
034
           return MP_OKAY;
035
        }
036
037
        if ((res = mp_init_copy (&t, a)) != MP_OKAY) {
038
          return res;
039
040
041
        /* if it is negative output a - */
042
        if (t.sign == MP_NEG) {
043
          ++_s;
044
          *str++ = '-';
045
          t.sign = MP_ZPOS;
046
        }
047
048
        digs = 0;
049
        while (mp_iszero (&t) == 0) {
          if ((res = mp_div_d (&t, (mp_digit) radix, &t, &d)) != MP_OKAY) \{
050
051
            mp_clear (&t);
052
            return res;
053
```

```
054
          *str++ = mp_s_rmap[d];
055
          ++digs;
056
057
        /\ast reverse the digits of the string. In this case \_\mathrm{s} points
058
        * to the first digit [exluding the sign] of the number]
059
060
         */
        bn_reverse ((unsigned char *)_s, digs);
061
062
063
        /* append a NULL so the string is properly terminated */
       *str = '\0';
064
065
066
        mp_clear (&t);
067
        return MP_OKAY;
068
      }
069
```

Chapter 9

Number Theoretic Algorithms

This chapter discusses several fundamental number theoretic algorithms such as the greatest common divisor, least common multiple and Jacobi symbol computation. These algorithms arise as essential components in several key cryptographic algorithms such as the RSA public key algorithm and various Sieve based factoring algorithms.

9.1 Greatest Common Divisor

The greatest common divisor of two integers a and b, often denoted as (a,b) is the largest integer k that is a proper divisor of both a and b. That is, k is the largest integer such that $0 \equiv a \pmod{k}$ and $0 \equiv b \pmod{k}$ occur simultaneously.

The most common approach (cite) is to reduce one input modulo another. That is if a and b are divisible by some integer k and if qa + r = b then r is also divisible by k. The reduction pattern follows $\langle a, b \rangle \to \langle b, a \mod b \rangle$.

```
Algorithm Greatest Common Divisor (I). Input. Two positive integers a and b greater than zero. Output. The greatest common divisor (a, b).
```

```
1. While (b > 0) do

1.1 r \leftarrow a \pmod{b}

1.2 a \leftarrow b

1.3 b \leftarrow r

2. Return(a).
```

Figure 9.1: Algorithm Greatest Common Divisor (I)

This algorithm will quickly converge on the greatest common divisor since the residue r tends diminish rapidly. However, divisions are relatively expensive operations to perform and should ideally be avoided. There is another approach based on a similar relationship of greatest common divisors. The faster approach is based on the observation that if k divides both a and b it will also divide a-b. In particular, we would like a-b to decrease in magnitude which implies that $b \geq a$.

```
Input. Two positive integers a and b greater than zero.
Output. The greatest common divisor (a, b).
1. While (b > 0) do
1.1 Swap a and b such that a is the smallest of the two.
1.2 b ← b − a
2. Return(a).
```

Algorithm Greatest Common Divisor (II).

Figure 9.2: Algorithm Greatest Common Divisor (II)

Proof Algorithm 9.2 will return the greatest common divisor of a and b. The algorithm in figure 9.2 will eventually terminate since $b \ge a$ the subtraction in step 1.2 will be a value less than b. In other words in every iteration that tuple $\langle a,b\rangle$ decrease in magnitude until eventually a=b. Since both a and b are always divisible by the greatest common divisor (until the last iteration) and in the last iteration of the algorithm b=0, therefore, in the second to last iteration of the algorithm b=a and clearly (a,a)=a which concludes the proof. **QED**.

As a matter of practicality algorithm 9.1 decreases far too slowly to be useful.

Specially if b is much larger than a such that b-a is still very much larger than a. A simple addition to the algorithm is to divide b-a by a power of some integer p which does not divide the greatest common divisor but will divide b-a. In this case $\frac{b-a}{p}$ is also an integer and still divisible by the greatest common divisor.

However, instead of factoring b-a to find a suitable value of p the powers of p can be removed from a and b that are in common first. Then inside the loop whenever b-a is divisible by some power of p it can be safely removed.

Algorithm Greatest Common Divisor (III). Input. Two positive integers a and b greater than zero.

```
Output. The greatest common divisor (a, b).
1. k \leftarrow 0
2. While a and b are both divisible by p do
  2.1 \ a \leftarrow |a/p|
  2.2 \ b \leftarrow |b/p|
  2.3 \ k \leftarrow k+1
3. While a is divisible by p do
  3.1 \ a \leftarrow |a/p|
4. While b is divisible by p do
  4.1 \ b \leftarrow |b/p|
5. While (b > 0) do
  5.1 Swap a and b such that a is the smallest of the two.
  5.2 \ b \leftarrow b - a
  5.3 While b is divisible by p do
     5.3.1 \ b \leftarrow \lfloor b/p \rfloor
6. Return(a \cdot p^k).
```

Figure 9.3: Algorithm Greatest Common Divisor (III)

This algorithm is based on the first except it removes powers of p first and inside the main loop to ensure the tuple $\langle a,b\rangle$ decreases more rapidly. The first loop on step two removes powers of p that are in common. A count, k, is kept which will present a common divisor of p^k . After step two the remaining common divisor of a and b cannot be divisible by p. This means that p can be safely divided out of the difference b-a so long as the division leaves no remainder.

In particular the value of p should be chosen such that the division on step 5.3.1 occur often. It also helps that division by p be easy to compute. The ideal

choice of p is two since division by two amounts to a right logical shift. Another important observation is that by step five both a and b are odd. Therefore, the diffrence b-a must be even which means that each iteration removes one bit from the largest of the pair.

9.1.1 Complete Greatest Common Divisor

The algorithms presented so far cannot handle inputs which are zero or negative. The following algorithm can handle all input cases properly and will produce the greatest common divisor.

```
Algorithm mp_gcd.
Input. mp_int a and b
Output. The greatest common divisor c = (a, b).
1. If a = 0 and b \neq 0 then
  1.1 \ c \leftarrow b
  1.2 Return(MP\_OKAY).
2. If a \neq 0 and b = 0 then
  2.1 \ c \leftarrow a
  2.2 Return(MP\_OKAY).
3. If a = b = 0 then
  3.1 \ c \leftarrow 1
  3.2 Return(MP\_OKAY).
4. \ u \leftarrow |a|, v \leftarrow |b|
5. k \leftarrow 0
6. While u.used > 0 and v.used > 0 and u_0 \equiv v_0 \equiv 0 \pmod{2}
  6.1 \ k \leftarrow k + 1
  6.2 \ u \leftarrow |u/2|
  6.3 \ v \leftarrow |v/2|
7. While u.used > 0 and u_0 \equiv 0 \pmod{2}
  7.1 \ u \leftarrow |u/2|
8. While v.used > 0 and v_0 \equiv 0 \pmod{2}
  8.1 \ v \leftarrow |v/2|
9. While v.used > 0
  9.1 If |u| > |v| then
     9.1.1 \text{ Swap } u \text{ and } v.
  9.2 \ v \leftarrow |v| - |u|
  9.3 While v.used > 0 and v_0 \equiv 0 \pmod{2}
     9.3.1 \ v \leftarrow \lfloor v/2 \rfloor
10. c \leftarrow u \cdot 2^k
11. Return(MP_{-}OKAY).
```

Figure 9.4: Algorithm mp_gcd

Algorithm mp_gcd. This algorithm will produce the greatest common divisor of two mp_ints a and b. The algorithm was originally based on Algorithm B of Knuth [1, pp. 338] but has been modified to be simpler to explain. In theory it achieves the same asymptotic working time as Algorithm B and in practice this appears to be true.

The first three steps handle the cases where either one of or both inputs are zero. If either input is zero the greatest common divisor is the largest input or

zero if they are both zero. If the inputs are not trivial than u and v are assigned the absolute values of a and b respectively and the algorithm will proceed to reduce the pair.

Step six will divide out any common factors of two and keep track of the count in the variable k. After this step two is no longer a factor of the remaining greatest common divisor between u and v and can be safely evenly divided out of either whenever they are even. Step seven and eight ensure that the u and v respectively have no more factors of two. At most only one of the while loops will iterate since they cannot both be even.

By step nine both of u and v are odd which is required for the inner logic. First the pair are swapped such that v is equal to or greater than u. This ensures that the subtraction on step 9.2 will always produce a positive and even result. Step 9.3 removes any factors of two from the difference u to ensure that in the next iteration of the loop both are once again odd.

After v = 0 occurs the variable u has the greatest common divisor of the pair $\langle u, v \rangle$ just after step six. The result must be adjusted by multiplying by the common factors of two (2^k) removed earlier.

```
File: bn_mp_gcd.c
016
017
      /* Greatest Common Divisor using the binary method */
      int mp_gcd (mp_int * a, mp_int * b, mp_int * c)
018
019
020
        mp_int u, v;
021
        int
                k, u_lsb, v_lsb, res;
022
023
        /* either zero than gcd is the largest */
        if (mp_iszero (a) == 1 && mp_iszero (b) == 0) {
024
025
          return mp_abs (b, c);
026
        if (mp_iszero (a) == 0 && mp_iszero (b) == 1) {
027
028
          return mp_abs (a, c);
029
0.30
031
        /* optimized. At this point if a == 0 then
         * b must equal zero too
032
033
         */
        if (mp_iszero (a) == 1) {
034
          mp_zero(c);
035
          return MP_OKAY;
036
037
```

```
038
039
        /* get copies of a and b we can modify */
040
        if ((res = mp_init_copy (&u, a)) != MP_OKAY) {
041
          return res;
042
043
044
        if ((res = mp_init_copy (&v, b)) != MP_OKAY) {
045
          goto __U;
046
047
048
        /* must be positive for the remainder of the algorithm */
049
        u.sign = v.sign = MP_ZPOS;
050
051
        /* B1. Find the common power of two for u and v */
052
        u_lsb = mp_cnt_lsb(&u);
053
        v_lsb = mp_cnt_lsb(&v);
054
             = MIN(u_lsb, v_lsb);
055
056
        if (k > 0) {
057
           /* divide the power of two out */
058
           if ((res = mp_div_2d(&u, k, &u, NULL)) != MP_OKAY) {
              goto __V;
059
060
061
062
           if ((res = mp_div_2d(&v, k, &v, NULL)) != MP_OKAY) {
063
              goto __V;
064
           }
065
        }
066
067
        /* divide any remaining factors of two out */
068
        if (u_lsb != k) {
069
           if ((res = mp_div_2d(&u, u_lsb - k, &u, NULL)) != MP_OKAY) {
070
              goto __V;
071
           }
        }
072
073
074
        if (v_lsb != k) {
075
           if ((res = mp_div_2d(&v, v_lsb - k, &v, NULL)) != MP_OKAY) {
076
              goto __V;
077
           }
078
        }
079
```

```
080
        while (mp_iszero(&v) == 0) {
           /* make sure v is the largest */
081
           if (mp_cmp_mag(\&u, \&v) == MP_GT) {
082
083
              /* swap u and v to make sure v is >= u */
084
              mp_exch(&u, &v);
085
086
087
           /* subtract smallest from largest */
           if ((res = s_mp_sub(&v, &u, &v)) != MP_OKAY) {
088
089
              goto __V;
090
091
092
           /* Divide out all factors of two */
           if ((res = mp_div_2d(&v, mp_cnt_lsb(&v), &v, NULL)) != MP_OKAY) {
093
094
              goto __V;
095
096
        }
097
098
        /* multiply by 2**k which we divided out at the beginning */
        if ((res = mp_mul_2d (&u, k, c)) != MP_OKAY) {
099
100
           goto __V;
101
102
        c->sign = MP_ZPOS;
103
        res = MP_OKAY;
104
      __V:mp_clear (&u);
      __U:mp_clear (&v);
105
106
        return res;
107
```

This function makes use of the macros mp_iszero and mp_iseven. The former evaluates to 1 if the input mp_int is equivalent to the integer zero otherwise it evaluates to 0. The latter evaluates to 1 if the input mp_int represents a non-zero even integer otherwise it evaluates to 0. Note that just because mp_iseven may evaluate to 0 does not mean the input is odd, it could also be zero. The three trivial cases of inputs are handled on lines 24 through 37. After those lines the inputs are assumed to be non-zero.

Lines 34 and 40 make local copies u and v of the inputs a and b respectively. At this point the common factors of two must be divided out of the two inputs. The while loop on line 80 iterates so long as both are even. The local integer k is used to keep track of how many factors of 2 are pulled out of both values. It is assumed that the number of factors will not exceed the maximum value of a

C "int" data type 1 .

At this point there are no more common factors of two in the two values. The while loops on lines 80 and 80 remove any independent factors of two such that both u and v are guaranteed to be an odd integer before hitting the main body of the algorithm. The while loop on line 80 performs the reduction of the pair until v is equal to zero. The unsigned comparison and subtraction algorithms are used in place of the full signed routines since both values are guaranteed to be positive and the result of the subtraction is guaranteed to be non-negative.

9.2 Least Common Multiple

The least common multiple of a pair of integers is their product divided by their greatest common divisor. For two integers a and b the least common multiple is normally denoted as [a,b] and numerically equivalent to $\frac{ab}{(a,b)}$. For example, if $a=2\cdot 2\cdot 3=12$ and $b=2\cdot 3\cdot 3\cdot 7=126$ the least common multiple is $\frac{126}{(12,126)}=\frac{126}{6}=21$.

The least common multiple arises often in coding theory as well as number theory. If two functions have periods of a and b respectively they will collide, that is be in synchronous states, after only [a, b] iterations. This is why, for example, random number generators based on Linear Feedback Shift Registers (LFSR) tend to use registers with periods which are co-prime (e.g. the greatest common divisor is one.). Similarly in number theory if a composite n has two prime factors p and q then maximal order of any unit of $\mathbb{Z}/n\mathbb{Z}$ will be [p-1, q-1].

```
Algorithm mp_lcm.
Input. mp_int a and b
Output. The least common multiple c = [a, b].

1. c \leftarrow (a, b)
2. t \leftarrow a \cdot b
3. c \leftarrow \lfloor t/c \rfloor
4. Return(MP\_OKAY).
```

Figure 9.5: Algorithm mp_lcm

Algorithm mp_lcm. This algorithm computes the least common multiple

¹Strictly speaking no array in C may have more than entries than are accessible by an "int" so this is not a limitation.

of two mp_int inputs a and b. It computes the least common multiple directly by dividing the product of the two inputs by their greatest common divisor.

```
File: bn_mp_lcm.c
017
      /* computes least common multiple as |a*b|/(a, b) */
018
      int mp_lcm (mp_int * a, mp_int * b, mp_int * c)
019
020
        int
                res;
021
        mp_int t1, t2;
022
023
024
        if ((res = mp_init_multi (&t1, &t2, NULL)) != MP_OKAY) {
025
          return res;
026
027
028
        /* t1 = get the GCD of the two inputs */
        if ((res = mp_gcd (a, b, &t1)) != MP_OKAY) {
029
030
          goto __T;
031
032
033
        /* divide the smallest by the GCD */
034
        if (mp_cmp_mag(a, b) == MP_LT) {
           /* store quotient in t2 such that t2 * b is the LCM */
035
           if ((res = mp_div(a, &t1, &t2, NULL)) != MP_OKAY) {
036
037
              goto __T;
038
039
           res = mp_mul(b, &t2, c);
040
        } else {
           /* store quotient in t2 such that t2 * a is the LCM */
041
042
           if ((res = mp_div(b, &t1, &t2, NULL)) != MP_OKAY) {
043
              goto __T;
044
           }
045
           res = mp_mul(a, &t2, c);
046
047
048
        /* fix the sign to positive */
049
        c->sign = MP_ZPOS;
050
      __T:
051
052
        mp_clear_multi (&t1, &t2, NULL);
053
        return res;
054
      }
```

9.3 Jacobi Symbol Computation

To explain the Jacobi Symbol we shall first discuss the Legendre function² off which the Jacobi symbol is defined. The Legendre function computes whether or not an integer a is a quadratic residue modulo an odd prime p. Numerically it is equivalent to equation 9.1.

$$a^{(p-1)/2} \equiv \begin{array}{c} -1 & \text{if a is a quadratic non-residue.} \\ 0 & \text{if a divides p.} \qquad (\text{mod p}) \\ 1 & \text{if a is a quadratic residue.} \end{array}$$

Proof. Equation 9.1 correctly identifies the residue status of an integer a modulo a prime p. An integer a is a quadratic residue if the following equation has a solution.

$$x^2 \equiv a \pmod{p} \tag{9.2}$$

Consider the following equation.

$$0 \equiv x^{p-1} - 1 \equiv \left\{ \left(x^2 \right)^{(p-1)/2} - a^{(p-1)/2} \right\} + \left(a^{(p-1)/2} - 1 \right) \pmod{p} \qquad (9.3)$$

Whether equation 9.2 has a solution or not equation 9.3 is always true. If $a^{(p-1)/2} - 1 \equiv 0 \pmod{p}$ then the quantity in the braces must be zero. By reduction,

$$(x^{2})^{(p-1)/2} - a^{(p-1)/2} \equiv 0$$

$$(x^{2})^{(p-1)/2} \equiv a^{(p-1)/2}$$

$$x^{2} \equiv a \pmod{p}$$
(9.4)

As a result there must be a solution to the quadratic equation and in turn a must be a quadratic residue. If a does not divide p and a is not a quadratic residue then the only other value $a^{(p-1)/2}$ may be congruent to is -1 since

$$0 \equiv a^{p-1} - 1 \equiv (a^{(p-1)/2} + 1)(a^{(p-1)/2} - 1) \pmod{p}$$
(9.5)

One of the terms on the right hand side must be zero. **QED**

²Arrg. What is the name of this?

9.3.1 Jacobi Symbol

The Jacobi symbol is a generalization of the Legendre function for any odd non prime moduli p greater than 2. If $p = \prod_{i=0}^{n} p_i$ then the Jacobi symbol $\left(\frac{a}{p}\right)$ is equal to the following equation.

$$\left(\frac{a}{p}\right) = \left(\frac{a}{p_0}\right) \left(\frac{a}{p_1}\right) \dots \left(\frac{a}{p_n}\right) \tag{9.6}$$

By inspection if p is prime the Jacobi symbol is equivalent to the Legendre function. The following facts³ will be used to derive an efficient Jacobi symbol algorithm. Where p is an odd integer greater than two and $a, b \in \mathbb{Z}$ the following are true.

- 1. $\left(\frac{a}{p}\right)$ equals -1, 0 or 1.
- $2. \left(\frac{ab}{p}\right) = \left(\frac{a}{p}\right) \left(\frac{b}{p}\right).$
- 3. If $a \equiv b$ then $\left(\frac{a}{p}\right) = \left(\frac{b}{p}\right)$.
- 4. $\left(\frac{2}{p}\right)$ equals 1 if $p \equiv 1$ or 7 (mod 8). Otherwise, it equals -1.
- 5. $\left(\frac{a}{p}\right) \equiv \left(\frac{p}{a}\right) \cdot (-1)^{(p-1)(a-1)/4}$. More specifically $\left(\frac{a}{p}\right) = \left(\frac{p}{a}\right)$ if $p \equiv a \equiv 1 \pmod{4}$.

Using these facts if $a = 2^k \cdot a'$ then

$$\left(\frac{a}{p}\right) = \left(\frac{2^k}{p}\right) \left(\frac{a'}{p}\right) \\
= \left(\frac{2}{p}\right)^k \left(\frac{a'}{p}\right) \tag{9.7}$$

By fact five,

$$\left(\frac{a}{p}\right) = \left(\frac{p}{a}\right) \cdot (-1)^{(p-1)(a-1)/4} \tag{9.8}$$

 $^{^3}$ See HAC [2, pp. 72-74] for further details.

Subsequently by fact three since $p \equiv (p \mod a) \pmod a$ then

$$\left(\frac{a}{p}\right) = \left(\frac{p \mod a}{a}\right) \cdot (-1)^{(p-1)(a-1)/4} \tag{9.9}$$

By putting both observations into equation 9.7 the following simplified equation is formed.

$$\left(\frac{a}{p}\right) = \left(\frac{2}{p}\right)^k \left(\frac{p \mod a'}{a'}\right) \cdot (-1)^{(p-1)(a'-1)/4} \tag{9.10}$$

The value of $\left(\frac{p \mod a'}{a'}\right)$ can be found by using the same equation recursively. The value of $\left(\frac{2}{p}\right)^k$ equals 1 if k is even otherwise it equals $\left(\frac{2}{p}\right)$. Using this approach the factors of p do not have to be known. Furthermore, if (a,p)=1 then the algorithm will terminate when the recursion requests the Jacobi symbol computation of $\left(\frac{1}{a'}\right)$ which is simply 1.

```
Input. mp_int a and p, a \ge 0, p \ge 3, p \equiv 1 \pmod{2}
Output. The Jacobi symbol c = \left(\frac{a}{p}\right).
1. If a = 0 then
   1.1 \ c \leftarrow 0
   1.2 Return(MP\_OKAY).
2. If a=1 then
  2.1 c \leftarrow 1
  2.2 \operatorname{Return}(MP\_OKAY).
3. \ a' \leftarrow a
4. k \leftarrow 0
5. While a'.used > 0 and a'_0 \equiv 0 \pmod{2}
  5.1 \ k \leftarrow k + 1
  5.2~a' \leftarrow \lfloor a'/2 \rfloor
6. If k \equiv 0 \pmod{2} then
  6.1\ s \leftarrow 1
7. else
  7.1 \ r \leftarrow p_0 \pmod{8}
   7.2 If r = 1 or r = 7 then
      7.2.1\ s \leftarrow 1
  7.3 else
     7.3.1 s \leftarrow -1
8. If p_0 \equiv a_0' \equiv 3 \pmod{4} then
  8.1\ s \leftarrow -s
9. If a' \neq 1 then
  9.1 \ p' \leftarrow p \pmod{a'}
  9.2 \ s \leftarrow s \cdot \text{mp\_jacobi}(p', a')
10. c \leftarrow s
11. Return(MP\_OKAY).
```

Algorithm mp_jacobi.

Figure 9.6: Algorithm mp_jacobi

Algorithm mp_jacobi. This algorithm computes the Jacobi symbol for an arbitrary positive integer a with respect to an odd integer p greater than three. The algorithm is based on algorithm 2.149 of HAC [2, pp. 73].

Step numbers one and two handle the trivial cases of a=0 and a=1 respectively. Step five determines the number of two factors in the input a. If k is even than the term $\left(\frac{2}{p}\right)^k$ must always evaluate to one. If k is odd than the term evaluates to one if p_0 is congruent to one or seven modulo eight, otherwise

it evaluates to -1. After the the $\left(\frac{2}{p}\right)^k$ term is handled the $(-1)^{(p-1)(a'-1)/4}$ is computed and multiplied against the current product s. The latter term evaluates to one if both p and a' are congruent to one modulo four, otherwise it evaluates to negative one.

By step nine if a' does not equal one a recursion is required. Step 9.1 computes $p' \equiv p \pmod{a'}$ and will recurse to compute $\binom{p'}{a'}$ which is multiplied against the current Jacobi product.

```
File: bn_mp_jacobi.c
016
017
      /* computes the jacobi c = (a | n) (or Legendre if n is prime)
018
       * HAC pp. 73 Algorithm 2.149
019
      int mp_jacobi (mp_int * a, mp_int * p, int *c)
020
021
022
        mp_int a1, p1;
023
        int
                k, s, r, res;
024
        mp_digit residue;
025
026
        /* if p <= 0 return MP_VAL */</pre>
027
        if (mp_cmp_d(p, 0) != MP_GT) {
028
           return MP_VAL;
029
        }
030
031
        /* step 1. if a == 0, return 0 */
        if (mp_iszero (a) == 1) {
032
033
          *c = 0;
034
          return MP_OKAY;
035
        }
036
037
        /* step 2. if a == 1, return 1 */
038
        if (mp\_cmp\_d (a, 1) == MP\_EQ) {
039
          *c = 1;
040
          return MP_OKAY;
041
042
043
        /* default */
044
        s = 0;
045
        /* step 3. write a = a1 * 2**k */
046
        if ((res = mp_init_copy (&a1, a)) != MP_OKAY) {
047
```

```
048
          return res;
049
050
051
        if ((res = mp_init (&p1)) != MP_OKAY) {
052
          goto __A1;
053
054
055
        /* divide out larger power of two */
056
        k = mp_cnt_lsb(\&a1);
        if ((res = mp_div_2d(&a1, k, &a1, NULL)) != MP_OKAY) {
057
058
           goto __P1;
059
        }
060
        /* step 4. if e is even set s=1 */
061
062
        if ((k \& 1) == 0) {
063
          s = 1;
064
        } else {
065
          /* else set s=1 if p = 1/7 \pmod{8} or s=-1 if p = 3/5 \pmod{8} */
066
          residue = p->dp[0] & 7;
067
          if (residue == 1 || residue == 7) {
068
069
            s = 1;
070
          } else if (residue == 3 || residue == 5) {
071
            s = -1;
072
          }
073
        }
074
075
        /* step 5. if p == 3 \pmod{4} *and* a1 == 3 \pmod{4} then s = -s */
076
        if ((p->dp[0] & 3) == 3) & ((a1.dp[0] & 3) == 3))
077
          s = -s;
078
        }
079
080
        /* if a1 == 1 we're done */
081
        if (mp\_cmp\_d (\&a1, 1) == MP\_EQ) {
082
          *c = s;
083
        } else {
084
          /* n1 = n mod a1 */
085
          if ((res = mp_mod (p, &a1, &p1)) != MP_OKAY) {
            goto __P1;
086
087
088
          if ((res = mp_jacobi (&p1, &a1, &r)) != MP_OKAY) {
089
            goto __P1;
```

As a matter of practicality the variable a' as per the pseudo-code is reprensented by the variable a1 since the 'symbol is not valid for a C variable name character.

The two simple cases of a=0 and a=1 are handled at the very beginning to simplify the algorithm. If the input is non-trivial the algorithm has to proceed compute the Jacobi. The variable s is used to hold the current Jacobi product. Note that s is merely a C "int" data type since the values it may obtain are merely -1, 0 and 1.

After a local copy of a is made all of the factors of two are divided out and the total stored in k. Technically only the least significant bit of k is required, however, it makes the algorithm simpler to follow to perform an addition. In practice an exclusive-or and addition have the same processor requirements and neither is faster than the other.

Line 61 through 70 determines the value of $\left(\frac{2}{p}\right)^k$. If the least significant bit of k is zero than k is even and the value is one. Otherwise, the value of s depends on which residue class p belongs to modulo eight. The value of $(-1)^{(p-1)(a'-1)/4}$ is compute and multiplied against s on lines 75 through 73.

Finally, if a1 does not equal one the algorithm must recurse and compute $\left(\frac{p'}{a'}\right)$.

- Comment about default s and such...

9.4 Modular Inverse

The modular inverse of a number actually refers to the modular multiplicative inverse. Essentially for any integer a such that (a,p)=1 there exist another integer b such that $ab \equiv 1 \pmod{p}$. The integer b is called the multiplicative inverse of a which is denoted as $b=a^{-1}$. Technically speaking modular inversion is a well defined operation for any finite ring or field not just for rings and fields of integers. However, the former will be the matter of discussion.

The simplest approach is to compute the algebraic inverse of the input. That is to compute $b \equiv a^{\Phi(p)-1}$. If $\Phi(p)$ is the order of the multiplicative subgroup modulo p then b must be the multiplicative inverse of a. The proof of which is trivial.

$$ab \equiv a \left(a^{\Phi(p)-1} \right) \equiv a^{\Phi(p)} \equiv a^0 \equiv 1 \pmod{p}$$
 (9.11)

However, as simple as this approach may be it has two serious flaws. It requires that the value of $\Phi(p)$ be known which if p is composite requires all of the prime factors. This approach also is very slow as the size of p grows.

A simpler approach is based on the observation that solving for the multiplicative inverse is equivalent to solving the linear Diophantine⁴ equation.

$$ab + pq = 1 \tag{9.12}$$

Where a, b, p and q are all integers. If such a pair of integers $\langle b, q \rangle$ exist than b is the multiplicative inverse of a modulo p. The extended Euclidean algorithm (Knuth [1, pp. 342]) can be used to solve such equations provided (a, p) = 1. However, instead of using that algorithm directly a variant known as the binary Extended Euclidean algorithm will be used in its place. The binary approach is very similar to the binary greatest common divisor algorithm except it will produce a full solution to the Diophantine equation.

9.4.1 General Case

⁴See LeVeque [?, pp. 40-43] for more information.

259

```
Algorithm mp_invmod.
Input. mp_int a and b, (a, b) = 1, p \ge 2, 0 < a < p.
Output. The modular inverse c \equiv a^{-1} \pmod{b}.
1. If b \leq 0 then return(MP_-VAL).
2. If b_0 \equiv 1 \pmod{2} then use algorithm fast_mp_invmod.
3. x \leftarrow |a|, y \leftarrow b
4. If x_0 \equiv y_0 \equiv 0 \pmod{2} then \operatorname{return}(MP_{-}VAL).
5. \ B \leftarrow 0, C \leftarrow 0, A \leftarrow 1, D \leftarrow 1
6. While u.used > 0 and u_0 \equiv 0 \pmod{2}
   6.1 \ u \leftarrow |u/2|
   6.2 If (A.used > 0 \text{ and } A_0 \equiv 1 \pmod{2}) or (B.used > 0 \text{ and } B_0 \equiv 1 \pmod{2}) then
     6.2.1 A \leftarrow A + y
     6.2.2~B \leftarrow B - x
   6.3 A \leftarrow \lfloor A/2 \rfloor
   6.4 B \leftarrow |B/2|
7. While v.used > 0 and v_0 \equiv 0 \pmod{2}
   7.1 \ v \leftarrow |v/2|
   7.2 If (C.used > 0 \text{ and } C_0 \equiv 1 \pmod{2}) or (D.used > 0 \text{ and } D_0 \equiv 1 \pmod{2}) then
     7.2.1 \ C \leftarrow C + y
     7.2.2 D \leftarrow D - x
   7.3 \ C \leftarrow |C/2|
   7.4 D \leftarrow |D/2|
8. If u \geq v then
   8.1 \ u \leftarrow u - v
  8.2~A \leftarrow A - C
   8.3 B \leftarrow B - D
9. else
  9.1 \ v \leftarrow v - u
  9.2~C \leftarrow C - A
  9.3~D \leftarrow D - B
10. If u \neq 0 goto step 6.
11. If v \neq 1 return(MP_{-}VAL).
12. While C \leq 0 do
   12.1 \ C \leftarrow C + b
13. While C \geq b do
   13.1 \ C \leftarrow C - b
14. c \leftarrow C
15. Return(MP\_OKAY).
```

Algorithm mp_invmod. This algorithm computes the modular multi-

plicative inverse of an integer a modulo an integer b. This algorithm is a variation of the extended binary Euclidean algorithm from HAC [2, pp. 608]. It has been modified to only compute the modular inverse and not a complete Diophantine solution.

If $b \leq 0$ than the modulus is invalid and MP_VAL is returned. Similarly if both a and b are even then there cannot be a multiplicative inverse for a and the error is reported.

The astute reader will observe that steps seven through nine are very similar to the binary greatest common divisor algorithm mp_gcd. In this case the other variables to the Diophantine equation are solved. The algorithm terminates when u=0 in which case the solution is

$$Ca + Db = v (9.13)$$

If v, the greatest common divisor of a and b is not equal to one then the algorithm will report an error as no inverse exists. Otherwise, C is the modular inverse of a. The actual value of C is congruent to, but not necessarily equal to, the ideal modular inverse which should lie within $1 \le a^{-1} < b$. Step numbers twelve and thirteen adjust the inverse until it is in range. If the original input a is within 0 < a < p then only a couple of additions or subtractions will be required to adjust the inverse.

```
File: bn_mp_invmod.c
016
      /* hac 14.61, pp608 */
017
018
      int mp_invmod (mp_int * a, mp_int * b, mp_int * c)
019
020
        mp_int x, y, u, v, A, B, C, D;
021
        int
                res;
022
        /* b cannot be negative */
023
024
        if (b->sign == MP_NEG || mp_iszero(b) == 1) {
025
          return MP_VAL;
026
027
        /* if the modulus is odd we can use a faster routine instead */
028
029
        if (mp_isodd (b) == 1) {
030
          return fast_mp_invmod (a, b, c);
031
032
033
        /* init temps */
```

```
034
        if ((res = mp_init_multi(&x, &y, &u, &v,
035
                                  &A, &B, &C, &D, NULL)) != MP_OKAY) {
036
           return res;
037
038
039
        /* x = a, y = b */
040
        if ((res = mp_copy (a, &x)) != MP_OKAY) {
041
          goto __ERR;
042
043
        if ((res = mp_copy (b, &y)) != MP_OKAY) {
044
          goto __ERR;
045
        }
046
047
        /* 2. [modified] if x,y are both even then return an error! */
048
        if (mp_iseven (&x) == 1 && mp_iseven (&y) == 1) {
049
          res = MP_VAL;
050
          goto __ERR;
051
052
        /* 3. u=x, v=y, A=1, B=0, C=0,D=1 */
053
        if ((res = mp_copy (&x, &u)) != MP_OKAY) \{
054
055
          goto __ERR;
056
        if ((res = mp_copy (&y, &v)) != MP_OKAY) {
057
058
          goto __ERR;
059
060
        mp_set (&A, 1);
061
        mp_set (&D, 1);
062
063
      top:
064
        /* 4. while u is even do */
065
        while (mp_iseven (&u) == 1) {
066
          /* 4.1 u = u/2 */
067
          if ((res = mp_div_2 (&u, &u)) != MP_OKAY) {
068
            goto __ERR;
069
070
          /* 4.2 if A or B is odd then */
          if (mp_isodd (&A) == 1 || mp_isodd (&B) == 1) {
071
            /* A = (A+y)/2, B = (B-x)/2 */
072
073
            if ((res = mp_add (&A, &y, &A)) != MP_OKAY) {
074
               goto __ERR;
075
```

```
076
            if ((res = mp_sub (&B, &x, &B)) != MP_OKAY) {
077
               goto __ERR;
078
            }
079
080
          /* A = A/2, B = B/2 */
081
          if ((res = mp_div_2 (&A, &A)) != MP_OKAY) {
082
            goto __ERR;
083
          if ((res = mp_div_2 (&B, &B)) != MP_OKAY) {
084
085
            goto __ERR;
086
087
        }
088
089
        /* 5. while v is even do */
090
        while (mp_iseven (&v) == 1) {
091
          /* 5.1 v = v/2 */
092
          if ((res = mp_div_2 (&v, &v)) != MP_OKAY) {
093
            goto __ERR;
094
          /* 5.2 if C or D is odd then */
095
          if (mp_isodd (&C) == 1 || mp_isodd (&D) == 1) {
096
097
            /* C = (C+y)/2, D = (D-x)/2 */
            if ((res = mp_add (&C, &y, &C)) != MP_OKAY) {
098
099
               goto __ERR;
100
            if ((res = mp_sub (&D, &x, &D)) != MP_OKAY) {
101
102
               goto __ERR;
            }
103
104
105
          /* C = C/2, D = D/2 */
106
          if ((res = mp_div_2 (&C, &C)) != MP_OKAY) {
107
            goto __ERR;
108
109
          if ((res = mp_div_2 (&D, &D)) != MP_OKAY) {
110
            goto __ERR;
111
112
113
        /* 6. if u \ge v then */
114
        if (mp_cmp (&u, &v) != MP_LT) {
115
          /* u = u - v, A = A - C, B = B - D */
116
117
          if ((res = mp_sub (&u, &v, &u)) != MP_OKAY) {
```

```
118
            goto __ERR;
119
120
121
          if ((res = mp_sub (&A, &C, &A)) != MP_OKAY) {
122
            goto __ERR;
123
124
125
          if ((res = mp_sub (&B, &D, &B)) != MP_OKAY) {
126
            goto __ERR;
127
128
        } else {
129
          /* v - v - u, C = C - A, D = D - B */
130
          if ((res = mp_sub (&v, &u, &v)) != MP_OKAY) {
            goto __ERR;
131
132
          }
133
134
          if ((res = mp_sub (&C, &A, &C)) != MP_OKAY) {
135
            goto __ERR;
136
137
138
          if ((res = mp_sub (&D, &B, &D)) != MP_OKAY) {
            goto __ERR;
139
140
141
        }
142
143
        /* if not zero goto step 4 */
144
        if (mp_iszero (&u) == 0)
145
          goto top;
146
147
        /* now a = C, b = D, gcd == g*v */
148
149
        /* if v != 1 then there is no inverse */
150
        if (mp_cmp_d (&v, 1) != MP_EQ) {
151
          res = MP_VAL;
152
          goto __ERR;
153
154
155
        /* if its too low */
        while (mp\_cmp\_d(\&C, 0) == MP\_LT) {
156
            if ((res = mp_add(&C, b, &C)) != MP_OKAY) {
157
158
               goto __ERR;
159
            }
```

```
}
160
161
        /* too big */
162
163
        while (mp_cmp_mag(&C, b) != MP_LT) {
164
             if ((res = mp_sub(&C, b, &C)) != MP_OKAY) {
165
                goto __ERR;
             }
166
        }
167
168
169
        /* C is now the inverse */
170
        mp_exch (&C, c);
        res = MP_OKAY;
171
172
      __ERR:mp_clear_multi (&x, &y, &u, &v, &A, &B, &C, &D, NULL);
173
        return res;
174
      }
```

Odd Moduli

When the modulus b is odd the variables A and C are fixed and are not required to compute the inverse. In particular by attempting to solve the Diophantine Cb + Da = 1 only B and D are required to find the inverse of a.

The algorithm fast_mp_invmod is a direct adaptation of algorithm mp_invmod with all all steps involving either A or C removed. This optimization will halve the time required to compute the modular inverse.

9.5 Primality Tests

A non-zero integer a is said to be prime if it is not divisible by any other integer excluding one and itself. For example, a=7 is prime since the integers 2...6 do not evenly divide a. By contrast, a=6 is not prime since $a=6=2\cdot 3$.

Prime numbers arise in cryptography considerably as they allow finite fields to be formed. The ability to determine whether an integer is prime or not quickly has been a viable subject in cryptography and number theory for considerable time. The algorithms that will be presented are all probablistic algorithms in that when they report an integer is composite it must be composite. However, when the algorithms report an integer is prime the algorithm may be incorrect.

As will be discussed it is possible to limit the probability of error so well that for practical purposes the probability of error might as well be zero. For the purposes of these discussions let n represent the candidate integer of which the primality is in question.

9.5.1 Trial Division

Trial division means to attempt to evenly divide a candidate integer by small prime integers. If the candidate can be evenly divided it obviously cannot be prime. By dividing by all primes 1 this test can actually prove whether an integer is prime. However, such a test would require a prohibitive amount of time as <math>n grows.

Instead of dividing by every prime, a smaller, more mangeable set of primes may be used instead. By performing trial division with only a subset of the primes less than $\sqrt{n} + 1$ the algorithm cannot prove if a candidate is prime. However, often it can prove a candidate is not prime.

The benefit of this test is that trial division by small values is fairly efficient. Specially compared to the other algorithms that will be discussed shortly. The probability that this approach correctly identifies a composite candidate when tested with all primes upto q is given by $1 - \frac{1.12}{ln(q)}$. The graph (??, will be added later) demonstrates the probability of success for the range $3 \le q \le 100$.

At approximately q=30 the gain of performing further tests diminishes fairly quickly. At q=90 further testing is generally not going to be of any practical use. In the case of LibTomMath the default limit q=256 was chosen since it is not too high and will eliminate approximately 80% of all candidate integers. The constant **PRIME_SIZE** is equal to the number of primes in the test base. The array __prime_tab is an array of the first **PRIME_SIZE** prime numbers.

```
Algorithm mp_prime_is_divisible.

Input. mp_int a
Output. c = 1 if n is divisible by a small prime, otherwise c = 0.

1. for ix from 0 to PRIME\_SIZE do
1.1 d \leftarrow n \pmod{\_prime\_tab_{ix}}
1.2 If d = 0 then
1.2.1 c \leftarrow 1
1.2.2 Return(MP\_OKAY).

2. c \leftarrow 0
3. Return(MP\_OKAY).
```

Figure 9.7: Algorithm mp_prime_is_divisible

Algorithm mp_prime_is_divisible. This algorithm attempts to deter-

mine if a candidate integer n is composite by performing trial divisions.

```
File: bn_mp_prime_is_divisible.c
016
017
      /* determines if an integers is divisible by one
018
       * of the first PRIME_SIZE primes or not
019
020
       * sets result to 0 if not, 1 if yes
021
       */
022
      int mp_prime_is_divisible (mp_int * a, int *result)
023
024
        int
                 err, ix;
025
        mp_digit res;
026
027
        /* default to not */
028
        *result = MP_NO;
029
        for (ix = 0; ix < PRIME_SIZE; ix++) {</pre>
030
031
          /* what is a mod __prime_tab[ix] */
032
          if ((err = mp_mod_d (a, __prime_tab[ix], &res)) != MP_OKAY) {
033
            return err;
034
035
036
          /* is the residue zero? */
037
          if (res == 0) {
            *result = MP_YES;
038
039
            return MP_OKAY;
040
          }
041
042
043
        return MP_OKAY;
044
```

The algorithm defaults to a return of 0 in case an error occurs. The values in the prime table are all specified to be in the range of a mp_digit. The table __prime_tab is defined in the following file.

```
021
      #ifndef MP_8BIT
022
        0x0083.
        0x0089, 0x008B, 0x0095, 0x0097, 0x009D, 0x00A3, 0x00A7, 0x00AD,
023
024
        0x00B3, 0x00B5, 0x00BF, 0x00C1, 0x00C5, 0x00C7, 0x00D3, 0x00DF,
025
        0x00E3, 0x00E5, 0x00E9, 0x00EF, 0x00F1, 0x00FB, 0x0101, 0x0107,
026
        0x010D, 0x010F, 0x0115, 0x0119, 0x011B, 0x0125, 0x0133, 0x0137,
027
028
        0x0139, 0x013D, 0x014B, 0x0151, 0x015B, 0x015D, 0x0161, 0x0167,
        0x016F, 0x0175, 0x017B, 0x017F, 0x0185, 0x018D, 0x0191, 0x0199,
029
        0x01A3, 0x01A5, 0x01AF, 0x01B1, 0x01B7, 0x01BB, 0x01C1, 0x01C9,
030
        0x01CD, 0x01CF, 0x01D3, 0x01DF, 0x01E7, 0x01EB, 0x01F3, 0x01F7,
031
032
        0x01FD, 0x0209, 0x020B, 0x021D, 0x0223, 0x022D, 0x0233, 0x0239,
        0x023B, 0x0241, 0x024B, 0x0251, 0x0257, 0x0259, 0x025F, 0x0265,
033
        0x0269, 0x026B, 0x0277, 0x0281, 0x0283, 0x0287, 0x028D, 0x0293,
034
035
        0x0295, 0x02A1, 0x02A5, 0x02AB, 0x02B3, 0x02BD, 0x02C5, 0x02CF,
036
037
        0x02D7, 0x02DD, 0x02E3, 0x02E7, 0x02EF, 0x02F5, 0x02F9, 0x0301,
038
        0x0305, 0x0313, 0x031D, 0x0329, 0x032B, 0x0335, 0x0337, 0x033B,
039
        0x033D, 0x0347, 0x0355, 0x0359, 0x035B, 0x035F, 0x036D, 0x0371,
        0x0373, 0x0377, 0x038B, 0x038F, 0x0397, 0x03A1, 0x03A9, 0x03AD,
040
        0x03B3, 0x03B9, 0x03C7, 0x03CB, 0x03D1, 0x03D7, 0x03DF, 0x03E5,
041
042
        0x03F1, 0x03F5, 0x03FB, 0x03FD, 0x0407, 0x0409, 0x040F, 0x0419,
        0x041B, 0x0425, 0x0427, 0x042D, 0x043F, 0x0443, 0x0445, 0x0449,
043
        0x044F, 0x0455, 0x045D, 0x0463, 0x0469, 0x047F, 0x0481, 0x048B,
044
045
046
        0x0493, 0x049D, 0x04A3, 0x04A9, 0x04B1, 0x04BD, 0x04C1, 0x04C7,
        0x04CD, 0x04CF, 0x04D5, 0x04E1, 0x04EB, 0x04FD, 0x04FF, 0x0503,
047
        0x0509, 0x050B, 0x0511, 0x0515, 0x0517, 0x051B, 0x0527, 0x0529,
048
049
        0x052F, 0x0551, 0x0557, 0x055D, 0x0565, 0x0577, 0x0581, 0x058F,
050
        0x0593, 0x0595, 0x0599, 0x059F, 0x05A7, 0x05AB, 0x05AD, 0x05B3,
051
        0x05BF, 0x05C9, 0x05CB, 0x05CF, 0x05D1, 0x05D5, 0x05DB, 0x05E7,
052
        0x05F3, 0x05FB, 0x0607, 0x060D, 0x0611, 0x0617, 0x061F, 0x0623,
053
        0x062B, 0x062F, 0x063D, 0x0641, 0x0647, 0x0649, 0x064D, 0x0653
054
      #endif
055
      };
```

Note that there are two possible tables. When an mp_digit is 7-bits long only the primes upto 127 may be included, otherwise the primes upto 1619 are used. Note that the value of **PRIME_SIZE** is a constant dependent on the size of a mp_digit.

9.5.2 The Fermat Test

The Fermat test is probably one the oldest tests to have a non-trivial probability of success. It is based on the fact that if n is in fact prime then $a^n \equiv a \pmod{n}$ for all 0 < a < n. The reason being that if n is prime than the order of the multiplicative sub group is n-1. Any base a must have an order which divides n-1 and as such a^n is equivalent to $a^1 = a$.

If n is composite then any given base a does not have to have a period which divides n-1. In which case it is possible that $a^n \not\equiv a \pmod{n}$. However, this test is not absolute as it is possible that the order of a base will divide n-1 which would then be reported as prime. Such a base yields what is known as a Fermat pseudo-prime. Several integers known as Carmichael numbers will be a pseudo-prime to all valid bases. Fortunately such numbers are extremely rare as n grows in size.

```
Algorithm mp_prime_fermat.

Input. mp_int a and b, a \ge 2, 0 < b < a.

Output. c = 1 if b^a \equiv b \pmod{a}, otherwise c = 0.

1. t \leftarrow b^a \pmod{a}
2. If t = b then
2.1 c = 1
3. else
3.1 c = 0
4. Return(MP\_OKAY).
```

Figure 9.8: Algorithm mp_prime_fermat

Algorithm mp_prime_fermat. This algorithm determines whether an mp_int a is a Fermat prime to the base b or not. It uses a single modular exponentiation to determine the result.

```
File: bn_mp_prime_fermat.c
016
017    /* performs one Fermat test.
018    *
019    * If "a" were prime then b**a == b (mod a) since the order of
020    * the multiplicative sub-group would be phi(a) = a-1. That means
021    * it would be the same as b**(a mod (a-1)) == b**1 == b (mod a).
022    *
023    * Sets result to 1 if the congruence holds, or zero otherwise.
```

```
024
       */
025
      int mp_prime_fermat (mp_int * a, mp_int * b, int *result)
026
027
        mp_int t;
028
        int
                err;
029
030
        /* default to composite */
031
        *result = MP NO:
032
        /* ensure b > 1 */
033
        if (mp_cmp_d(b, 1) != MP_GT) {
034
035
           return MP_VAL;
036
        }
037
038
        /* init t */
039
        if ((err = mp_init (&t)) != MP_OKAY) {
040
          return err;
041
042
        /* compute t = b**a mod a */
043
        if ((err = mp_exptmod (b, a, a, &t)) != MP_OKAY) {
044
045
          goto __T;
046
047
048
        /* is it equal to b? */
        if (mp_cmp (&t, b) == MP_EQ) {
049
050
          *result = MP_YES;
051
052
053
        err = MP_OKAY;
054
      __T:mp_clear (&t);
055
        return err;
056
```

9.5.3 The Miller-Rabin Test

The Miller-Rabin (citation) test is another primality test which has tighter error bounds than the Fermat test specifically with sequentially chosen candidate integers. The algorithm is based on the observation that if $n-1=2^kr$ and if $b^r \not\equiv \pm 1$ then after upto k-1 squarings the value must be equal to -1. The squarings are stopped as soon as -1 is observed. If the value of 1 is observed

first it means that some value not congruent to ± 1 when squared equals one which cannot occur if n is prime.

```
Algorithm mp_prime_miller_rabin.
Input. mp_int a and b, a \ge 2, 0 < b < a.
Output. c = 1 if a is a Miller-Rabin prime to the base a, otherwise c = 0.
1. a' \leftarrow a - 1
2. r \leftarrow n1
3. \ c \leftarrow 0, s \leftarrow 0
4. While r.used > 0 and r_0 \equiv 0 \pmod{2}
   4.1 \ s \leftarrow s + 1
   4.2 \ r \leftarrow |r/2|
5. y \leftarrow b^r \pmod{a}
6. If y \not\equiv \pm 1 then
   6.1 \ j \leftarrow 1
   6.2 While j \leq (s-1) and y \not\equiv a'
     6.2.1 \ y \leftarrow y^2 \pmod{a}
     6.2.2 \text{ If } y = 1 \text{ then goto step } 8.
     6.2.3 \ j \leftarrow j + 1
   6.3 If y \not\equiv a' goto step 8.
7. c \leftarrow 1
8. Return(MP_{-}OKAY).
```

Figure 9.9: Algorithm mp_prime_miller_rabin

Algorithm mp_prime_miller_rabin. This algorithm performs one trial round of the Miller-Rabin algorithm to the base b. It will set c=1 if the algorithm cannot determine if b is composite or c=0 if b is provably composite. The values of s and r are computed such that $a'=a-1=2^s r$.

If the value $y \equiv b^r$ is congruent to ± 1 then the algorithm cannot prove if a is composite or not. Otherwise, the algorithm will square y upto s-1 times stopping only when $y \equiv -1$. If $y^2 \equiv 1$ and $y \not\equiv \pm 1$ then the algorithm can report that a is provably composite. If the algorithm performs s-1 squarings and $y \not\equiv -1$ then a is provably composite. If a is not provably composite then it is probably prime.

```
File: bn_mp_prime_miller_rabin.c
016
017  /* Miller-Rabin test of "a" to the base of "b" as described in
018      * HAC pp. 139 Algorithm 4.24
019      *
```

```
020
       * Sets result to 0 if definitely composite or 1 if probably prime.
021
       * Randomly the chance of error is no more than 1/4 and often
022
       * very much lower.
023
       */
024
      int mp_prime_miller_rabin (mp_int * a, mp_int * b, int *result)
025
026
        mp_int n1, y, r;
027
        int
                s, j, err;
028
029
        /* default */
030
        *result = MP_NO;
031
032
        /* ensure b > 1 */
033
        if (mp_cmp_d(b, 1) != MP_GT) {
034
           return MP_VAL;
035
        }
036
037
        /* get n1 = a - 1 */
038
        if ((err = mp_init_copy (&n1, a)) != MP_OKAY) {
039
          return err;
040
041
        if ((err = mp_sub_d (&n1, 1, &n1)) != MP_OKAY) {
042
          goto __N1;
043
044
045
        /* set 2**s * r = n1 */
046
        if ((err = mp_init_copy (&r, &n1)) != MP_OKAY) {
047
          goto __N1;
048
        }
049
050
        /* count the number of least significant bits
051
        * which are zero
052
053
        s = mp_cnt_lsb(&r);
054
055
        /* now divide n - 1 by 2**s */
056
        if ((err = mp_div_2d (&r, s, &r, NULL)) != MP_OKAY) {
057
          goto __R;
058
        }
059
060
        /* compute y = b**r mod a */
        if ((err = mp_init (&y)) != MP_OKAY) {
061
```

```
062
          goto __R;
063
064
        if ((err = mp_exptmod (b, &r, a, &y)) != MP_OKAY) {
065
          goto __Y;
066
067
068
        /* if y != 1 and y != n1 do */
069
        if (mp_cmp_d (&y, 1) != MP_EQ && mp_cmp (&y, &n1) != MP_EQ) {
070
          j = 1;
071
          /* while j <= s-1 and y != n1 */
072
          while ((j \le (s - 1)) \&\& mp_cmp (\&y, \&n1) != MP_EQ) 
073
            if ((err = mp_sqrmod (&y, a, &y)) != MP_OKAY) {
074
               goto __Y;
075
076
077
            /* if y == 1 then composite */
078
            if (mp\_cmp\_d (\&y, 1) == MP\_EQ) {
079
               goto __Y;
            }
080
081
082
            ++j;
          }
083
084
085
          /* if y != n1 then composite */
086
          if (mp_cmp (&y, &n1) != MP_EQ) {
087
            goto __Y;
088
089
        }
090
091
        /* probably prime now */
092
        *result = MP_YES;
093
      __Y:mp_clear (&y);
      __R:mp_clear (&r);
094
095
      __N1:mp_clear (&n1);
096
        return err;
097
```

Bibliography

- [1] Donald Knuth, *The Art of Computer Programming*, Third Edition, Volume Two, Seminumerical Algorithms, Addison-Wesley, 1998
- [2] A. Menezes, P. van Oorschot, S. Vanstone, *Handbook of Applied Cryptography*, CRC Press, 1996
- [3] Michael Rosing, Implementing Elliptic Curve Cryptography, Manning Publications, 1999
- [4] Paul G. Comba, Exponentiation Cryptosystems on the IBM PC. IBM Systems Journal 29(4): 526-538 (1990)
- [5] A. Karatsuba, Doklay Akad. Nauk SSSR 145 (1962), pp.293-294
- [6] Andre Weimerskirch and Christof Paar, Generalizations of the Karatsuba Algorithm for Polynomial Multiplication, Submitted to Design, Codes and Cryptography, March 2002
- [7] Paul Barrett, Implementing the Rivest Shamir and Adleman Public Key Encryption Algorithm on a Standard Digital Signal Processor, Advances in Cryptology, Crypto '86, Springer-Verlag.
- [8] P.L.Montgomery. Modular multiplication without trial division. Mathematics of Computation, 44(170):519-521, April 1985.
- [9] Chae Hoon Lim and Pil Joong Lee, Generating Efficient Primes for Discrete Log Cryptosystems, POSTECH Information Research Laboratories
- [10] J. Daemen and R. Govaerts and J. Vandewalle, *Block ciphers based on Modular Arithmetic*, State and Progress in the Research of Cryptography, 1993, pp. 80-89

[11]	R.L. Rivest, A. Shamir, L. Adleman, A Method for Obtaining Digital Signatures and Public-Key Cryptosystems
[12]	Whitfield Diffie, Martin E. Hellman, New Directions in Cryptography, IEEE Transactions on Information Theory, 1976
[13]	IEEE Standard for Binary Floating-Point Arithmetic (ANSI/IEEE St d $754\text{-}1985)$
[14]	GNU Multiple Precision (GMP), http://www.swox.com/gmp/
[15]	Multiple Precision Integer Library (MPI), Michael Fromberger, http://thayer.dartmouth.edu/~sting/mpi/
[16]	OpenSSL Cryptographic Toolkit, http://openssl.org
[17]	Large Integer Package, http://home.hetnet.nl/~ecstr/LIP.zip
[18]	$\rm JTC1/SC22/WG14, ISO/IEC$ 9899:1999, "A draft rationale for the C99 standard."
[19]	The Sun Java Website, http://java.sun.com/

Index

```
baseline multiplication, 88 big-Oh, 7\,
```

modular residue, 141 mp_digit, 5 mp_int, 5, 15 MP_MEM, 18 MP_NEG, 16 MP_OKAY, 18 MP_VAL, 18 mp_word, 5 MP_ZPOS, 16

precision, 3

radix point, 105